

625-EMD-004

EOSDIS Maintenance and Development Project

Training Material for the EMD Project Volume 4: System Administration

Revision 02

July 2006

Raytheon Company
Upper Marlboro, Maryland

Training Material for the EMD Project


Volume 4: System Administration

Revision 02

July 2006

Prepared Under Contract NAS5-03098
CDRL Item 23


RESPONSIBLE AUTHOR



Laywan Gamble and Debra Stepp
EOSDIS Maintenance and Development Project

July 27 2006
Date

RESPONSIBLE OFFICE



Mary Armstrong, Program Manager
EOSIDS Maintenance and Development Project

7/27/2006

Date

Raytheon Company
Upper Marlboro, Maryland

This page intentionally left blank.

Preface

This document is a formal contract deliverable. It requires Government review and approval within 45 business days. Changes to this document will be made by document change notice (DCN) or by complete revision.

Any questions should be addressed to:

Data Management Office
The EMD Project Office
Raytheon Company
1616 McCormick Drive
Upper Marlboro, Maryland 20774-5301

Revision History

Document Number	Status/Issue	Publication Date	CCR Number
625-EMD-004	Original	July 2004	04-0384
625-EMD-004	Revision 01	July 2005	05-0320
625-EMD-004	Revision 02	July 2006	06-0377

This page intentionally left blank.

Abstract

This is Volume 4 of a series of lessons containing the training material for the Earth Observing System Data and Information System (EOSDIS) Maintenance and Development (EMD) Project. This lesson provides a detailed description of the process required for creating, modifying, and implementing production requests and production plans and monitoring the processing of data processing requests.

Keywords: training, instructional design, course objective, production request, production plan, data processing request, production, planning, processing, Release 7.

This page intentionally left blank.

Contents

Preface

Abstract

Contents

Introduction

Identification	1
Scope	1
Purpose	1
Status and Schedule	1
Organization	1

Related Documentation

Parent Documents	3
Applicable Documents	3
Information Documents	3
Information Documents Referenced	3
Information Documents Not Referenced	4

System Administration Overview

Lesson Overview	7
Lesson Objectives	7
Importance	9

Secure Shell (SSH)

Secure Access to DAACs	11
Setting Up SSH.....	11
Remote SSH Access	12
Changing Your Passphrase	13
Logging in to System Hosts.....	14

System Startup and Shutdown

Cold Startup By Subsystem	16
Warm Startup	17
Updating leapsec.dat and utcpole.dat Files.....	18
Normal Shutdown	19
Emergency Shutdown	21
System Shutdown by Server	22

Checking the Health and Status of the System

WhatsUp Professional 2006 (Premium Edition).....	23
Launching WhatsUp Professional and Displaying the Device Group.....	24
Responding to Color Alerts and Obtaining Status of a Node	25
Configuring a Popup Menu for a Node or Multiple Nodes	26
Using Network Tools	29
Using WhatsUp Professional Reports.....	35
Whazzup???	36
Host Status	39
Verify Mode.....	39
Performance Management	39
ECS Health Check GUI	39
Starting and Using the ECS Health Check GUI	50
ECS Assistant and ECS Monitor	52

Tape Operations

Networker Administrator Screen	57
Labeling Tapes.....	58
Indexing Tapes.....	61

System Backups and Restores

Incremental Backup	67
Full System Backup	70
Single or Multiple File Restore.....	72
Complete System Restore	76

User Administration

Screening Personnel.....	81
Screening Criteria	81
Screening Procedures.....	81
Adding a New User.....	82
Deleting a User	82
Changing a User's Account Configuration.....	84
Changing User Access Privileges	84
Changing a User Password	85
Checking a File/Directory Access Privilege Status	85
Changing a File/Directory Access Privilege.....	86
Moving a User's Home Directory	89

Commercial Off-the-Shelf (COTS) Software Administration

Installation	91
LOG FILES.....	91
COTS Configuration.....	91

Security

Generating Security Reports	93
User Activity Data	93
User Audit Trail Information	94

Practical Exercise

System Startup and Shutdown	97
Tape Operations, System Backup and Restore	97
User Administration.....	98
System Maintenance	99

Slide Presentation

Slide Presentation Description.....	101
-------------------------------------	-----

Introduction

Identification

Training Material Volume 4 is part of Contract Data Requirements List (CDRL) Item 23, which is a required deliverable under the Earth Observing System Data and Information System (EOSDIS) Maintenance and Development (EMD) Contract (NAS5-03098).

Scope

Training Material Volume 4 describes the procedures by which the system administrator performs system administration activities. This lesson is designed to provide the operations staff with sufficient knowledge and information to satisfy all lesson objectives.

Purpose

The purpose of this Student Guide is to provide a detailed course of instruction that forms the basis for understanding system administration. Lesson objectives are developed and will be used to guide the flow of instruction for this lesson. The lesson objectives will serve as the basis for verifying that all lesson topics are contained within this Student Guide and slide presentation material.

Status and Schedule

This lesson module provides detailed information about training for the current baseline of the system. Revisions are submitted as needed.

Organization

This document is organized as follows:

Introduction:	The Introduction presents the document identification, scope, purpose, and organization.
Related Documentation:	Related Documentation identifies parent, applicable and information documents associated with this document.
Student Guide:	The Student Guide identifies the core elements of this lesson. All Lesson Objectives and associated topics are included.
Slide Presentation:	Slide Presentation is reserved for all slides used by the instructor during the presentation of this lesson.

This page intentionally left blank.

Related Documentation

Parent Documents

The parent documents are the documents from which the EMD Training Material's scope and content are derived.

423-41-01	Goddard Space Flight Center, EOSDIS Core System (ECS) Statement of Work
423-46-03	EMD Task 101 Statement of Work For ECS SDPS Maintenance
423-46-02	Contract Data Requirements Document for EMD Task 101 ECS SDPS Maintenance

Applicable Documents

The following documents are referenced within this EMD Training Material, or are directly applicable, or contain policies or other directive matters that are binding upon the content of this document:

420-05-03	Goddard Space Flight Center, Earth Observing System (EOS) Performance Assurance Requirements for the EOSDIS Core System (ECS)
423-41-02	Goddard Space Flight Center, Functional and Performance Requirements Specification for the Earth Observing System Data and Information System (EOSDIS) Core System (ECS) (ECS F&PRS)
423-46-01	Goddard Space Flight Center, Functional and Performance Requirements Specification for the Earth Observing System Data and Information System (EOSDIS) Core System (ECS) Science Data Processing System (EMD F&PRS)

Information Documents

Information Documents Referenced

The following documents are referenced herein and amplify or clarify the information presented in this document. These documents are not binding on the content of the EMD Training Material.

290-004	Goddard Space Flight Center, Internet Protocol Operational Network (IONet) Access Protection Policy and Requirements
335-EMD-002	EMD COTS Deployment Plan
609-EMD-001	Release 7.11 Operations Tools Manual for the EMD Project

611-EMD-001	Release 7.11 Mission Operation Procedures for the EMD Project
910-TDA-022	Custom Code Configuration Parameters for ECS
914-TDA-337	WhatsUp Professional 2006 Premium Maintenance Upgrade for EOSDIS Core System (ECS): Release Notes
NPR 1600.1	NASA Procedural Requirements: NASA Security Program Procedural Requirements
NPR 2810.1	NASA Procedural Requirements: Security of Information Technology
OMB Circular A-130	Office of Management and Budget, Management of Federal Information Resources

Information Documents Not Referenced

The following documents, although not referenced herein and/or not directly applicable, do amplify or clarify the information presented in this document. These documents are not binding on the content of the EMD Training Material.

305-EMD-001	Release 7.11 Segment/Design Specification for the EMD Project
311-EMD-001	Data Management Subsystem (DMS) Database Design and Database Schema Specifications for the EMD Project
311-EMD-002	INGEST (INS) Database Design and Schema Specifications for the EMD Project
311-EMD-003	Planning and Data Processing Subsystem Database Design and Schema Specifications for the EMD Project
311-EMD-004	Science Data Server Database Design and Schema Specifications for the EMD Project
311-EMD-005	Storage Management and Data Distribution Subsystems Database Design and Database Schema Specifications for the EMD Project
311-EMD-006	Subscription Server Database Design and Schema Specifications for the EMD Project
311-EMD-007	Systems Management Subsystem Database Design and Schema Specifications for the EMD Project
311-EMD-008	Registry Database Design and Schema Specifications for the EMD Project
311-EMD-009	Product Distribution Subsystem (PDS) Database Design and Database Schema Specifications for the EMD Project
311-EMD-010	NameServer Database Design and Schema Specifications for the EMD Project
311-EMD-011	Order Manager Database Design and Database Schema Specifications for the EMD Project

311-EMD-012	Spatial Subscription Server (SSS) Database Design and Schema Specifications for the EMD Project
311-EMD-013	Data Pool Database Design and Schema Specifications for the EMD Project
313-EMD-001	Release 7.11 Internal Interface Control Document for the EMD Project
508-EMD-001	ACRONYMS for the EOSDIS Maintenance and Development (EMD) Project
152-TP-003	Glossary of Terms for the EOSDIS Core System (ECS) Project

This page intentionally left blank.

System Administration Overview

Lesson Overview

This lesson will provide you with the tools needed to perform the various tasks required to administer Implementation of the Earth Observing System Data and Information System (EOSDIS) Core System (ECS) during maintenance and operations.

Lesson Objectives

Overall Objective - The overall objective of this lesson is proficiency in the various tasks required to perform system administration activities during maintenance and operations.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will use the Procedures Manual in accordance with prescribed methods and complete required procedures without error to accomplish all tasks required.

Specific Objective 1 - The student will perform a Secure Shell login to the system and establish a personal passphrase.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to login to the system using Secure Shell and establish a personal passphrase.

Specific Objective 2 - The student will manually shutdown and restart a single subsystem of the system without affecting other subsystems.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to effect an orderly shutdown and startup of one subsystem of the system without compromising or otherwise affecting the other component subsystems from the command line.

Specific Objective 3 - The student will shutdown and restart a single subsystem of the system using ECS Assistant without affecting other subsystems.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to effect an orderly shutdown and startup of one subsystem of the system without compromising or otherwise affecting the other component subsystems using the ECS Assistant.

Specific Objective 4 - The student will conduct system performance monitoring, to include using WhatsUp Professional 2006 (Premium Edition) to check the health and status of the network and accessing the EOSDIS Mission Support Network (EMSn) Web Page.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will use Whazzup and ECS Monitor in accordance with specified procedures and without error to check the status of system servers.

Specific Objective 5 - The student will label and index a tape cartridge.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to label a tape and index a tape cartridge.

Specific Objective 6 - The student will create an incremental tape backup.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to create an incremental tape backup of system files created or modified within the past six days.

Specific Objective 7 - The student will create a tape backup of the entire system.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to perform a complete tape backup of the system.

Specific Objective 8 - The student will restore individual files or entire volumes of backup tapes to the system.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to perform individual or complete file restorations.

Specific Objective 9 - The student will review and modify system logs.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to perform system log maintenance.

Specific Objective 10 - The student will create, modify, and delete user accounts on the system.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to add a new user account to the system, make modifications to a variety of account access parameters, and delete the account from the system.

Specific Objective 11 - The student will check and modify access privileges on files and directories across the system.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to check file and directory access privileges and modify them to allow or deny access by various classes of users.

Specific Objective 12 - The student will determine when security breaches occur and will remedy such breaches.

Condition - The student will be given a copy of 609-EMD-001, *Release 7.11 Operations Tools Manual for the EMD Project*, a copy of 611-EMD-001, *Release 7.11 Mission Operation Procedures for the EMD Project* and a functioning system.

Standard - The student will perform without error the procedures required to identify when security breaches occur and to remedy such breaches.

Importance

A System Administrator's goal is to keep the computer system usable by the users. A system running at peak efficiency does so because of the proper use of the tools provided for and used by the System Administrator. Intimate knowledge of how each tool works and which should be used in a particular situation is crucial to satisfying the user community.

This page intentionally left blank.

Secure Shell (SSH)

Secure Shell (ssh) is an application that greatly improves network security. Secure Shell is the standard for remote logins, solving the problem of hackers stealing passwords. Secure Shell secures connections by encrypting passwords and other data. Once launched, it provides transparent, strong authentication and secure communications over any IP-based connection. The SSH Secure Shell application is virtually invisible during day-to-day use. It provides a provides an extensive library of features for securing and authenticating terminal connections, file transfers or almost any other type of connection might be created over an IP network. Secure Shell is to be used for communication among system platforms and among the DAACs.

Secure Access to DAACs

The Local Area Network (LAN) that has been implemented at the DAACs is more secure than most other LANs. From the Internet, it is not possible to directly connect with all hosts at a DAAC. There is a set of hosts that are dual-homed to a user LAN that is connected on one side to the Internet and to the DAAC production LAN on the other side. This will require an interactive user to first use SSH to access a dual homed host and then use ssh to access a production host. In order to minimize the impact on the user, a single login has been implemented.

Setting Up SSH

SSH programs have client and server components much like other network programs. The user only needs to be concerned with the client configuration as the server side is set up by a systems administrator. The amount of effort that it takes to get SSH going depends on how many different home directories the user has. At Landover, for instance, there are separate directories for the EDF and the VATC.

Most users will start from the same host whether from an X terminal, a UNIX workstation or a PC. Prior to executing **ssh** commands, use **setenv DISPLAY <IP address>:0.0** at your local host. To ensure system security, do not use the **setenv DISPLAY** command on subsequent hosts accessed via **ssh**. The process is started by running the **SSH setup (sss)** script, which will enable **ssh** to other hosts from which one may use the same home directory. The only thing you need to do before executing the script is to pick a good passphrase of at least 10 characters. You can, and should, use spaces and multiple words with numbers and misspellings and special characters. Note that passwords are NOT echoed back to the screen.

Initiating SSHSETUP

- 1 Log in into your normal UNIX workstation where your home directory resides.

- 2 Initiate Secure Shell setup by typing **sss** then press the **Return/Enter** key.
 - You will see an information statement:
Use a passphrase of at least 10 characters which should include numbers or special characters and MAY include spaces
 - 3 At the **New passphrase:** prompt type *passphrase* then press the **Return/Enter** key.
 - 4 At the **Retype new passphrase:** prompt type *passphrase* then press the **Return/Enter** key.
 - You will then see:
Initializing random number generator...
Generating p: Please wait while the program completes ...
%
 - This establishes the .ssh sub-directory in your <username>/home directory, creates the local ssh key, and creates the necessary files.
-

Remote SSH Access

If you need to access a host with a different home directory, you will need to run the **sshremote** script. This script sets up the destination host with the new set of keys and transfers the source (local) key to the destination and the destination key to the source. You must have an existing account on the remote host.

Setting Up Remote Access SSH

- 1 Log in into your normal Unix workstation where your home directory resides.
- 2 Initiate Secure Shell remote setup by typing **ssr** then press the **Return/Enter** key.
 - You will see the following prompt: Remote user name: (Default: <name>):

NOTE: User must first have an account on the remote system.

You have a local passphrase. Do you want to setup for:

- 1 VATC
- 2 EDF
- 3 GSFC DAAC
- 4 SMC
- 5 GSFC M and O
- 6 EDC DAAC
- 7 EDC M and O
- 8 LaRC DAAC
- 9 LaRC M and O

10 NSIDC DAAC
11 NSIDC M and O
x Exit from script
Select:

- 3 At the **Select:** prompt, type in the corresponding number to the desired host then press the **Return/Enter** key.
 - You will receive a message similar to the following:
Enter the password for the remote system: <password>
- 4 At the prompt **Enter existing passphrase for remote system:** type *<passphrase>* then press the **Return/Enter** key.
 - A prompt similar to the following will be displayed:
Working...

NOTE: The ssh keys at remote sites can be different from the local host ssh key.

Changing Your Passphrase

Another script has been developed to change your passphrase on the local host and then transfer the key to the other environments. The **ssh** keys for remote hosts will have to be changed separately. Use the following procedure to change your passphrase:

Changing Your Passphrase

- 1 Log in to your normal Unix workstation where your home directory resides.
 - Initiate passphrase change by typing **ssp** then press the **Return/Enter** key.
 - You will see an information statement:
Use a passphrase of at least 10 characters which should include numbers or special characters and MAY include spaces
- 2 At the **Old passphrase:** prompt type old *passphrase* then press the **Return/Enter** key.
- 3 At the **New passphrase:** prompt type *new passphrase* then press the **Return/Enter** key.

4 At the **Retype new passphrase:** prompt type *new_passphrase* then press the **Return/Enter** key.

- You will then see an information prompt similar to the following:

```
ssh-keygen will now be executed. Please wait for the prompt to Return!  
/home/userid/.ssh/authorized_keys permissions have already been set.  
%
```

Logging in to System Hosts

Logging in to system hosts is accomplished from a UNIX command line prompt. It is an initial set of steps that is performed when accomplishing many other tasks.

Logging in to system hosts starts with the assumption that the applicable hosts are operational and the operator has logged in to a workstation or X-term that has access to the applicable network in the system.

Log in to System Hosts

NOTE: Commands in Steps 1 and 2 are typed at a UNIX system prompt.

1 In the terminal window (at the command line prompt) start the log-in to the appropriate host by typing **ssh <hostname>** then press the **Return/Enter** key.

- The **-l** option can be used with the ssh command to allow logging in to the remote host (or the local host for that matter) with a different user ID. For example, to log in to x0ins01 as user cmops enter:

```
/ssh -l cmops x0ins01
```

- Depending on the set-up it may or may not be necessary to include the path (i.e., /usr/local/bin/) with the ssh command. Using ssh alone is often adequate. For example:

```
ssh x0ins01
```

- or -

```
ssh -l cmops x0ins01
```

- Examples of Sun Consolidation External Server host names include **e0ins01**, **g0ins01**, **l0ins01**, and **n0ins02**.
- Examples of Sun Consolidation Internal Server host names include **e0acs11**, **g0acs11**, **l0acs03**, and **n0acs04**.

- If you receive the message, “**Host key not found from the list of known hosts. Are you sure you want to continue connecting (yes/no)?**” enter **yes** (“y” alone will not work).
 - If you have previously set up a secure shell passphrase and executed **sshremote**, a prompt to **Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase, go to Step 4.
- 2** If a prompt to **Passphrase for key '<user@localhost>'** appears, type your *<passphrase>* then press the **Return/Enter** key.
- If a command line prompt is displayed, log-in is complete.
 - If the passphrase is unknown, press the **Return/Enter** key, which should cause a **<user@remotehost>'s password:** prompt to appear (after the second or third try if not after the first one), then go to Step 4.
 - If the passphrase is entered improperly, a **<user@remotehost>'s password:** prompt should appear (after the second or third try if not after the first one); go to Step 4.
- 3** If a prompt for **<user@remotehost>'s password:** appears, type your *password* then press the **Return/Enter** key.
- A command line prompt is displayed.
 - Log-in is complete.
-

System Startup and Shutdown

Starting or shutting down a computer system may involve nothing more than turning a power switch to the on or off position. However, the interdependency of the various servers may require the System Administrator to startup or shutdown the servers in a particular order. Depending on the situation, the entire computer system may be started or stopped (cold) or only selected servers may be started or stopped (warm). The next sections cover the procedures and details of cold and warm startups and shutdowns.

A complete system startup and shutdown should only need to occur approximately once in three or four months during the early stages of system implementation due to the inherent instability of new systems. After the system stabilizes, it is estimated that complete system startups and shutdowns will occur only about once a year. Partial shutdowns and restarts will be performed as needed due to maintenance concerns.

Cold Startup By Subsystem

A cold startup is indicated when there are no subsystems currently running, e.g., when the system is to be turned on for the first time, following a system maintenance operation that requires all power to be turned off, or following a power failure. In most situations a cold startup is also indicated by the power switch being in the OFF position.

Performing Cold Subsystem Startup

- 1 Determine which machines perform the following functions (some machines may perform multiple functions).
 - Domain Name Server (DNS) Master
 - Name Information Server (NIS) Master
 - Mail Hub Server(s)
 - Automount Servers
 - ClearCase Server
 - Communication Subsystem (CSS)
 - Other License Servers
 - Sybase ASE Servers
 - Data Server Subsystem (DSS)
 - Planning & Data Processing System (PDPS)
 - Client Subsystem (CLS)

- 2 Startup the DNS Master, the NIS Master, and the CSS server.
 - Once that system has booted without error, proceed to Step 3.
 - 3 Power on the ClearCase server(s).
 - Once the systems(s) have booted without error, proceed to Step 4.
 - 4 Power on the Interface server(s).
 - Once the system(s) have booted without error, proceed to Step 5.
 - 5 Power on the MSS server(s).
 - Once the system(s) have booted without error, proceed to Step 6.
 - 6 Power on the DSS server(s).
 - Once the system(s) have booted without error, proceed to Step 7.
 - 7 Power on the Ingest server(s).
 - Once the system(s) have booted without error, proceed to Step 8.
 - 8 Power on the PDPS server(s).
 - Once the system(s) have booted without error, proceed to Step 9.
 - 9 Power on the Client and Data Management server(s).
-

Warm Startup

A warm startup is indicated when there are some subsystems currently running while others have been shutdown either due to operator intervention or an external malfunction. The subsystems not actively running need to be started without interfering with the current active operations. In some instances, a warm startup may require some active subsystems to be shutdown and restarted so that their interaction and connectivity will be properly resumed.

Performing Warm Subsystem Startup

- 1 Determine which machines perform the following functions:
 - Domain Name Server (DNS) Master
 - Name Information Server (NIS) Master
 - Mail Hub Server(s)
 - Automount Servers
 - ClearCase Server

- Communication Subsystem (CSS)
 - Other License Servers
 - System Management Subsystem
 - Sybase ASE Servers
 - Data Server Subsystem (DSS)
 - Planning & Data Processing System (PDPS)
 - Client Subsystem (CLS)
- 2 Determine which machine is currently down.
 - 3 Determine the interoperability dependencies among the machines.
 - 4 Turn on machines in an order consistent with the dependencies.

NOTE: In addition to warm system startup/reboot sequences, system servers that use the Sybase ASE server may need to be bounced whenever the ASE server is bounced. At present, this is certainly the case for all STMGT servers. That is, if the Sybase ASE server is stopped and restarted for any reason, all STMGT servers need to be stopped and restarted once the Sybase ASE server has come back on-line.

Updating leapsec.dat and utcpole.dat Files

In order to ensure proper operation of Product Generation Executives (PGEs), two files must be updated weekly with data transferred from the U.S. Naval Observatory. These files are `${PGSHOME}/database/common/TD/leapsec.dat` and `${PGSHOME}/database/common/CSC/utcpole.dat`. The updating of these files is accomplished by executing `leapsec_update.sh` and `utcpole_update.sh` in the `/usr/ecs/OPS/CUSTOM/TOOLKIT/toolkit/bin/sgi64_daac_f77` directory on each Science Processor with root privileges. If the tasks have not been set up to be accomplished via cron job, they must be done manually.

Updating leapsec.dat and utcpole.dat Files

NOTE: The user account performing the update must have write permission in the Toolkit directories.

- 1 Log in to one of the Science Processor machines.
 - Examples of Science Processor host names include **e0spg11**, **g0spg01**, and **l0spg11**.
- 2 Type `cd /usr/ecs/MODE/CUSTOM/TOOLKIT/toolkit/bin/sgi64_daac_f77` then press the **Return/Enter** key.
- 3 Type `source pgs-env.csh` then press the **Return/Enter** key.

- 4 Type either **update_leapsec.sh** (to update the leap seconds file) or **update_utcpole.sh** (to update the leap seconds file) as appropriate then press the **Return/Enter** key.
 - 5 Type responses to program prompts as appropriate.
 - 6 Repeat Steps 4 and 5 to update the other file.
 - 7 Repeat Steps 1 through 6 for each additional Science Processor host (if any).
-

Normal Shutdown

A normal shutdown occurs when the operator is required to turn off the power to the entire system or any of the component subsystems. The Resource Manager schedules normal shutdowns (with prior approval of DAAC management) at a time that minimizes disruption to system users, e.g., during off-hours. No loss of data is anticipated from a normal shutdown. All subsystems are shut down in a routine fashion.

The system shutdown procedure is performed by the System Administrator at the discretion of the Network Administrator, usually for the purpose of repair. The system shutdown is normally performed in reverse order of the system startup as previously described. Prior to a normal shutdown, the System Administrator sends broadcast messages to all Computer Operators on the system at Shutdown Minus 30 minutes, Shutdown Minus 15 minutes, and Shutdown Minus one minute. At the scheduled shutdown time, the System Administrator blocks all incoming requests from the gateway and allows active jobs to complete (unless it is anticipated that they will take longer than 10 minutes, in which case the System Administrator will terminate the processes and notify the originator). The System Administrator then begins to shut down all subsystems in the order prescribed in the procedure below.

When all subsystems have been successfully shutdown, the UNIX prompt appears on the console screen. Total time from shutdown initiation to completion may be as long as 45 minutes.

Performing Normal Shutdown by Subsystem

Steps 1 through 7 below are preliminary steps to shutting down each subsystem and are repeated (as necessary) for each subsystem.

- 1 Log in to the server as **root**.
- 2 Type **root_password** then press the **Return/Enter** key.
- 3 Type **wall** then press the **Return/Enter** key.
- 4 Type This machine is being shutdown for *reason*. Please save your work and log off now. We are sorry for the inconvenience. then press the **Ctrl** and **D** keys simultaneously.
- 5 Wait at least five minutes.
- 6 At the UNIX prompt type **shutdown -g0 -i0** or **shutdown now -i0** then press the **Return/Enter** key.

- 7 Power off all peripherals and the CPU.
- 8 Determine which machines perform the following functions:
 - DNS Master
 - NIS Master
 - Mail Hub Server(s)
 - Automount Server
 - ClearCase Server
 - CSS
 - CLS
 - Other License Servers
 - MSS including Sybase ASE Servers
 - DSS
 - Ingest
 - PDPS
- 9 Power off the CLS server by following Steps 1 through 7 above for the machine.
 - Once the system(s) have shutdown without error, proceed to Step 10.
- 10 Power off the PDPS server(s) by following Steps 1 through 7 above for each machine.
 - Once the system(s) have shutdown without error, proceed to Step 11.
- 11 Power off the Ingest server(s) by following Steps 1 through 7 above for each machine.
 - Once the system(s) have shutdown without error, proceed to Step 12.
- 12 Power off the DSS server(s) by following Steps 1 through 7 above for each machine.
 - Once the system(s) have shutdown without error, proceed to Step 13.
- 13 Power off the MSS server(s) by following Steps 1 through 7 above for each machine.
 - Once the system(s) have shutdown without error, proceed to Step 14.
- 14 Power off the Interface server(s) by following Steps 1 through 7 above for each machine.
 - Once the system(s) have shutdown without error, proceed to Step 15.
- 15 Power off the ClearCase server(s) by following Steps 1 through 7 above for each machine.
 - Once the system(s) have shutdown without error, proceed to Step 16.

- 16 Power off the CSS server, the NIS Master and the DNS Master by following Steps 1 through 7 above for each machine
-

Emergency Shutdown

An emergency shutdown is indicated when the System Administrator determines that the entire system or a component subsystem requires immediate maintenance. Indications that an emergency shutdown is in order include:

- The system or subsystem is locked up and users are unable to access or maneuver through the system
- An impending or actual power failure
- An actual system or subsystem hardware or software failure

Every effort should be made to minimize loss of data during an emergency shutdown by informing users to save files and log off if at all possible. However, circumstances may be such that a large-scale loss of data is unavoidable. In such instances, data will be restored from the most recent backup tapes and temporary backup files provided by the system (if applicable).

If the entire system is locked up then a complete system shutdown is required and the emergency shutdown and start-up procedures should be executed immediately. The DAAC manager is notified after the system has been brought back on line.

If major subsystems are locked up, a complete system shutdown is required and the emergency shutdown and start-up procedures should be executed immediately. The DAAC manager is notified after the system has been brought back on line.

If one or only a few of the subsystems are experiencing problems and only some of the users are affected, the subsystem problem(s) should be resolved first. If the System Administrator determines that all efforts to resolve the subsystem problems are exhausted and a shutdown is necessary, only the affected subsystems should be shutdown. Only if these steps provide no relief should the entire system be brought down. In any case, every effort should be made to accommodate users that are still on the system and to minimize data loss.

Performing Emergency Shutdown

- 1 Log in to the server as root.
- 2 Type *root_password* at the UNIX prompt then press the **Return/Enter** key.
- 3 Type **sync** at the UNIX prompt then press the **Return/Enter** key.
 - The **sync** command causes all information in memory that should be on disk to be written out including modified super blocks, modified inodes, and delayed block I/O. If the system is to be stopped, **sync** must be called to insure file system integrity.
- 4 Type **sync** (again) at the UNIX prompt then press the **Return/Enter** key.

- 5 Type **halt** at the UNIX prompt then press the **Return/Enter** key.
 - 6 Shutdown all client workstations.
 - 7 Determine which machines perform the following functions (some machines may perform multiple functions).
 - Sybase ASE/Rep
 - AutoSys
 - ClearCase
 - Automount
 - Mail Hub
 - NIS
 - DNS
 - 8 Power off the Sybase ASE/Rep server(s).
 - Once the system has shutdown without error, proceed to Step 9.
 - 9 Power off the AutoSys server(s).
 - Once the system has shutdown without error, proceed to Step 10.
 - 10 Power off the ClearCase server(s).
 - Once the system has shutdown without error, proceed to Step 11.
 - 11 Power off the Automount server(s).
 - Once the system has shutdown without error, proceed to Step 12.
 - 12 Power off the NIS server(s).
 - Once the system has shutdown without error, proceed to Step 13.
 - 13 Power off the DNS server(s).
-

System Shutdown by Server

In situations where only a single server requires maintenance, the System Administrator will need to determine if and how the faulty server affects other servers on the network. One server may be able to be shutdown without affecting the rest of the network, or several dependent servers may have to be shutdown in addition to the target server. Because of these interdependencies, each case will have to be uniquely evaluated.

Checking the Health and Status of the System

The system is heavily dependent on the use of computer networks. Graphical tools available to monitor system status include a COTS program, **WhatsUp Professional 2006 Premium Edition (WhatsUp Professional)**; three custom software programs, **ECS Assistant/ECS Monitor**, **EcMs-Whazzup??**, and the **ECS Health Check GUI**; and a script, **EcCsIdPingServers**, that permits an operator to ping all servers. These programs provide system monitors with real-time status of the system and indications of potential problem areas.

WhatsUp Professional 2006 (Premium Edition)

WhatsUp Professional 2006 Premium Edition (WhatsUp Professional) is a graphical network monitoring application selected to monitor critical devices and services on the Production Local Area Network (LAN) and/or additional DAAC networks. It initiates alerts when it detects problems, and can send remote notifications by beeper, pager, and e-mail. It logs events to facilitate troubleshooting and reporting. It is implemented on Windows XP on a Personal Computer (PC) connected to the Production LAN. Additional information on WhatsUp Professional is available in 609-EMD-001, Release 7.11 Operations Tools Manual for the EMD Project and the *WhatsUp Professional and Premium Edition 2006 User's Guide* vendor documentation, which is available on the Internet at the following URL:

http://www.ipswitch.com/Support/WhatsUp_professional/guides/2006/WUPUsersGuide2006.pdf

The procedures in this section assume that the installation procedure specified in Document 914-TDA-337, *WhatsUp Professional 2006 Premium Maintenance Upgrade for EOSDIS Core System (ECS): Release Notes*, has been executed. During the installation process the installer performs the following activities:

- Installs the WhatsUp Professional application.
- Creates a network map.
- Sets up network map alert notifications.
- Sets up a WinPopup notification message.
- Sets up an SMTP e-mail notification message.
- Sets the network map polling properties.
- Sets device properties.
- Saves the map.
- Starts WhatsUp Professional polling.

Once a network has been discovered by **WhatsUp Professional**, monitoring the state of the network can begin. Monitoring includes tasks such as checking the map for color alerts that indicate problems and checking for network changes.

Launching WhatsUp Professional and Displaying the Device Group

As noted previously, the WhatsUp Professional application and graphical user interface (GUI) are installed and run in the Windows environment on a PC. Once the application is started and being used to monitor the network, it is typically left running at all times. This is because the application must be running in order for its monitoring activities (i.e., polling and logging) to occur. Therefore, under normal circumstances, it will seldom be necessary to launch the application because it will be running continually. However, if something causes the application to stop (e.g., a failure of its host, or an inadvertent closure of the application), it will be necessary to start it again using the following procedure.




Figure 1. WhatsUp Professional Device Group

Launching WhatsUp Professional and Displaying the Network Map

- 1 Log on to the PC where WhatsUp Professional has been installed.
 - 2 Click on the **Start** button at the lower left corner of the PC monitor and select **All Programs → Ipswitch WhatsUp Professional 2006 Premium Edition → WhatsUp Professional Premium Edition** from menus.
 - The WhatsUp Professional main window is displayed.
 - 3 If the network map is not already open, select **File → Open** from the pull-down menu.
 - The **Open Device Group** dialog box is displayed.
 - 4 Double-click on a device group (or select the name with a single click and then click on the **OK** button).
 - The device view or map view of the devices in the group is displayed.
-

Responding to Color Alerts and Obtaining Status of a Node

Objects that have an abnormal condition can be identified by a change in appearance on the network map. Colors may be changed, but the following default conventions apply in a map window to indicate the status of a device or service:

- Device name highlighted: indicates that WhatsUp Professional has recorded an activity for the device in a log.
- Device icon on a green square background: indicates that the device is up (i.e., responds to polling).
- Device icon on a light green diamond-shaped background: indicates that the device has missed at least one polling request.
- Device icon on a yellow diamond-shaped background: indicates that the device has missed two polling requests.
- Device icon on a red elongated diamond-shaped background: indicates that the device is down (i.e., is not accessible or has missed four consecutive polling requests). Once the device has missed eight polling requests, the background is changed to a dark red starburst.
- Device icon on a light purple octagon-shaped background: indicates that a standard service on the device is down.
- Device on a gray square background: indicates monitoring has been turned off for the device.

A color alert on a symbol indicates that some part of that object may have problems. Placing your mouse's cursor on the symbol causes a brief description of the problem to appear on the status line at the bottom of the display. To help isolate a fault on the network further, it is possible to click with the right (or non-preferred) mouse button on the symbol with the color alert and bring up a variety of reports that provide more detailed information about the node based on TCP/IP polling, the Internet Control Message Protocol (ICMP) status, and the status of services on the node.

The following procedure is applicable for obtaining and reviewing the WhatsUp Professional response to color alerts and obtain the status of a node.

Responding to Color Alert and Obtaining the Status of a Node

NOTE: A node label is highlighted if there has been an entry in the Activity Log related to the alert and the background is other than a green square (or whatever you have selected as the indication for normal status).

- 1** With the network map open, use the right (or non-preferred) mouse button to click on the icon for a node showing a color alert.
 - A popup menu is displayed.
 - 2** On the popup menu, click on **Device Reports** . . .
 - A listing of available reports such as Device Status, Health, and State Change Timeline is displayed grouped by category. Click on the name of any report to view. When done reviewing the report, click the Map View tab at the bottom of the display to return to the network map.
 - 3** To acknowledge the alert select **Tools→Acknowledge** from the pull-down menu.
 - The highlighting is removed from the node label and additional instances of the alert on the node are prevented (unless the alert has been configured to be sent regardless of the acknowledgement, as described in the **User's Guide** and on-line **Help**).
-

Configuring a Popup Menu for a Node or Multiple Nodes

The popup menu accessible using the right (or non-preferred) mouse button to click on a node on a network map typically includes the following choices beyond the customary Copy, Past, Delete:

- **Display** – control the appearance of the display
- **Attach** – draw an attached line between two devices to show an arbitrary connection between devices. These are visual representations assigned by the user, and not reflections of true connectivity between the two devices; that is done with link lines.

- **Link** – set up connecting link lines on a map. Use Link lines to monitor the status of the network link (the Interface service) between two devices. Link lines can also show the status of any service which has an Active Monitor on the device.
- **Set Dependencies** – either “Set *Up Dependency* on or Set *Down Dependency* on to avoid turning off polling to devices, and instead make polling dependent on the status of another device in your database
- **Lock Position** – use Lock Position to keep an object from moving as you move other items around, or when adding devices to the map. If you want an object to be able to change positions on the map, remove the "lock position" selection.
- **Poll Now** – initiate a single poll of the network.
- **Acknowledge** – acknowledge the changed state of a device. This removes the device from Acknowledgment mode, which displays the name of the device in bold in the Device List and in a black background in Map View.
- **Device Reports. . .** – open the **Device Reports** dialog box to choose from a list of reports to display about the device.
- **Group Reports. . .** – open the **Group Reports** dialog box to choose from a list of reports to display about the device group.
- **4 Traceroute** – start the Traceroute tool to examine the network path and the intervening routers from the WhatsUp Professional machine to the device.
- **3 Ping** – start the Ping tool to send ICMP packets to the device and view the results.
- **2 Connect** – open a telnet session on the device represented by the node on the map.
- **1 Browse** – start the default browser using the IP address as the URL.
- **Remote Desktop. . .** – establish a connection with a terminal server or another computer running Windows.
- **Device Status Report. . .** -- display the **Device Status Report** for the device.
- **Properties . . .** – open the **Device Properties** dialog box to permit setting parameters for the device, including General functions, monitoring functions, services, alerts, and other categories (see **User’s Guide** or on-line **Help**).

The popup menu may be configured or customized for an individual device by selecting **Device Properties** dialog box. This will override – for the selected device – any context menu already created for the device type. .

The following procedure is applicable.

Configuring the Popup Menu for a Node or Multiple Nodes

- 1 On the network map, select the node(s) for which the popup menu is to be configured.
- 2 Use the right (or non-preferred) mouse button to click on the selected node
 - A popup menu is displayed.

- 3 On the popup menu, click on **Properties . . .**
 - The **Device Properties** dialog box is displayed to permit customization of the menu for that node.
 - Click on the **Customize the menu on this device (don't use device type menu** field to set the check box. This enables the **Add . . .**, **Edit . . .**, and **Remove . . .** buttons.
 - 4 To add a menu item, click on the **Add** button.
 - The **Edit Menu Item** dialog box is displayed with three empty fields:
 - **Display name:**
 - **Command:**
 - **Arguments:**
 - Using this box, it is possible to create a menu item for starting a program when the item is chosen.
 - The **Display name:** field is used to specify the name of the menu item that will appear in the popup menu.
 - The **Command:** field is used to enter the (file)name of any executable program to be started when the menu item is chosen from the popup menu.
 - The **Arguments:** field is used to pass parameters to the specified program.
 - See the **User's Guide** or on-line **Help** for detailed information on establishing and using popup menu items to run programs.
 - 5 To select a displayed menu item for editing or moving, click on the menu item in the list.
 - The selected item is highlighted.
 - 6 To edit a selected item, click on the **Edit** button.
 - The **Edit Menu Item** dialog box is displayed as in Step 4, with information for the selected item displayed in its three fields. The displayed data may be edited to change the menu display and/or actions (see **User's Guide** or on-line **Help**).
 - 7 To delete a selected item, click on the **Remove** button.
 - A confirmation dialog is displayed to ensure that you would like to remove the item.
 - 8 Click on the **Yes** button to confirm removal of the item.
 - 9 Click on the **OK** button.
 - The menu changes are applied and the **Device Properties** dialog is closed.
-

Using Network Tools

WhatsUp Professional provides a set of tools to display a variety of information about nodes on the network. These tools are displayed on tabs, with the parameters and results area for one tool on each tab. The tools include:

- **Info** – display a summary of device information.
- **Time** – synchronize your computer's clock with a remote time server.
- **HTML** – query a web address.
- **Ping** – verify connectivity to a host.
- **TraceRoute** – Trace and view the route to an Internet host.
- **Lookup** – query Internet domain name servers for information about hosts and name servers.
- **Finger** – display information about users on a host.
- **Whois** – display information from the network information center about Internet domain ownership and Internet groups.
- **LDAP** – (Lightweight Directory Access Protocol); search directories for names and information stored in an LDAP directory on another computer.
- **Quote** – view quotations from a quote server.
- **Scan** – scan a range of IP addresses to create a network map.
- **SNMP** – view and graph Simple Network Management Protocol (SNMP) values for a device.
- **WinNet** – View Windows Network domains, hosts, and workstations.
- **Throughput** – test data throughput on the connection between your computer and a remote computer.
- **System Info** – view information about your local system.


Not all of these tools are necessarily appropriate for DAAC use, but the **WhatsUp Professional User's Guide** and on-line **Help** provides detailed information on all of them. This lesson presents information on just three of them.

The **Info** tool, illustrated in Figure 4, displays a summary of information about a network host or device, including the official host name, IP address, and contact information. An Info request on a host name also pings the host to verify connectivity.

The following procedure is applicable for using the Net Tools Info Tool to obtain information on a node.

Use the Net Tools Info Tool to Obtain Information on a Node

- 1 Select **Tools**→**Net Tools** from the pull-down menu on the **WhatsUp Professional** GUI.
 - The **Net Tools** window is displayed.
- 2 If necessary, click on the **Info** tab to access the **Info** tab display (when the **Net Tools** window is opened, WhatsUp Professional displays the tab most recently accessed).



- The **Info** tab controls and fields are displayed.

Figure 4. WhatsUp Professional Net Tools - Info Tool

- 3 In the **Host Name or IP Address:** field, type the name or IP address of the host to be queried (this must be a fully qualified host name or address).
 - The typed entry is displayed in the field.
- 4 Click on the **Start** button.
 - A **Searching . . .** indicator appears and the **Start** button toggles to **Stop** to show that the query is in progress. At any time during the query, a click on the **Stop** button stops the query.
 - The results of the query are displayed. (A click on the **Clear** button erases the results from the display window.) The **List View/Report View** button permits toggling

between the **Report View** and the **List View** of the results. The **Report View** is a summary showing:

- Official Name.
 - Domain Name.
 - Date the record was created.
 - Date the record was last updated.
 - Date the database was last updated.
 - Contact information (from the Whois database).
 - IP Addresses and Domain Servers.
- The **List View** is a detailed list of the obtained information, including the results of the ping and more extensive information on the query.

The **Ping** tool, illustrated in Figure 5, is a network diagnostic tool used to verify connectivity to a selected system on the network. This tool sends a data packet (an ICMP “echo request”) to a remote host and displays the results for each “echo reply.” This pinging command also displays the time for a response to arrive in milliseconds, as well as debugging information about the network interface. Multiple instances of the **Ping** tool may be active simultaneously.




Figure 5. WhatsUp Professional Net Tools - Ping Tool

The use of the **Ping** tool provides a quick way to verify that a device is not functioning. If the ping operations do not produce any responses or they time out, then the node is probably down or otherwise unreachable over the network.

The following procedure is applicable for using the Net Tools Ping Tool to verify connectivity on a node.

Use the Net Tools Ping Tool to Verify Connectivity for a Node

- 1 Select **Tools→Net Tools. . .** from the pull-down menu on the **WhatsUp Professional** GUI.
 - The **Net Tools** window is displayed.
- 2 If necessary, click on the **Ping** tab to access the **Ping** tab display (when the **Net Tools** window is opened, WhatsUp Professional displays the tab most recently accessed).
 - The **Ping** tab controls and fields are displayed.
- 3 In the **Host Name or IP Address:** field, type the name or IP address of the host to be checked (this must be a fully qualified host name or address).
 - The typed entry is displayed in the field.
- 4 If it is desired to change the default number of pings to be sent, click at the end of the **Count:** field.
 - The cursor is displayed at the end of the **Count:** field.
- 5 To set a new value for **Count:** use the **Backspace** key to remove the current value, and type the new value.
 - The typed value appears in the **Count:** field.
- 6 Repeat Steps 5 and 6 for other options you wish to change, substituting **Delay (sec.):**, **Size**, or **Timeout (ms):** for the field name of the option to be changed, specifying respectively the number of seconds to wait between pings, the length in bytes of each packet to be sent by the **Ping** command, and the number of milliseconds of non-response from the host to be considered a failure of the ping.
- 8 Click on the **Start** button.
 - The **Start** button toggles to **Stop** to show that the ping operation is in progress. At any time during the operation, a click on the **Stop** button stops the pinging.
 - The display field at the bottom of the window shows the results of the pings.
 - A click on the **Clear** button erases the results from the display window.
 - The **List View/Report View** button permits toggling between the **Report View** and the **List View** of the results.

- 2 If necessary, click on the **Traceroute** tab to access the **Traceroute** tab display (when the **Net Tools** window is opened, WhatsUp Professional displays most recently accessed tab).
 - The **Traceroute** tab controls and fields are displayed.
- 3 In the **Host Name or IP Address:** field, type the name or IP address of the host to which the route is to be traced (this must be a fully qualified host name or address).
 - The typed entry is displayed in the field.
- 4 If it is desired to change the maximum number of hops to trace before ending the traceroute operation (a “hop” is the passing of an IP packet from one host to another), click at the end of the **Maximum Hopcount:** field.
 - The cursor is displayed at the end of the **Maximum Hopcount:** field.
- 5 To set a new value for **Maximum Hopcount:** use the **Backspace** key to remove the current value, and type the new value.
 - The typed value appears in the **Maximum Hopcount:** field.
- 6 If it is desired to change the number of milliseconds of non-response from the host to cause the Traceroute to fail, click at the end of the **Timeout (ms):** field.
 - The cursor is displayed at the end of the **Timeout (ms):** field.
- 7 To set a new value for **Timeout (ms):** use the **Backspace** key to remove the current value, and type the new value.
 - The typed value appears in the **Timeout (ms):** field.
- 8 If it is desired to specify that the host names of all routers along the route be displayed along with the IP addresses, click on the **Resolve Addresses** checkbox.
 - The clicked box displays a checkmark to indicate its selection, and when **Traceroute** is run, the host names as well as the IP addresses will be shown for each router (instead of just the IP addresses). This will add time to the Traceroute operation to resolve the IP addresses.
- 9 Click on the **Start** button.
 - An indicator shows the Traceroute operation in progress and the **Start** button toggles to **Stop** to show that the operation is in progress. At any time during the operation, a click on the **Stop** button stops the tracing.
 - The display field at the bottom of the window shows the results of the traceroute operation.
 - A click on the **Clear** button erases the results from the display window.

- The **List View/Report View** button permits toggling between the **Report View** and the **List View** of the results.
 - The **Report View** provides for each hop as it occurs the address, the response time or Round Trip Time (RTT), and the status.
 - The **List View** lists the hops, addresses, and more detailed information on the tracing of the route.

Using WhatsUp Professional Reports

WhatsUp Professional uses a single database to house all device information across all device groups. This information is accessible through a variety of reports.


Detailed information on the nature of the logged data is provided in the **User's Guide** and on-line **Help**. The **User's Guide** and on-line **Help** also describes how to change the way events are logged, and how to generate reports and graphs using the logged data to show the status of the network from various perspectives. Only the State Change Timeline report is described here, because of its potential utility in troubleshooting.

Reviewing the State Change Timeline Report

The State Change Timeline report presents a timeline of when each Monitor on a device in the selected group changed from one state to another during the displayed time period. For example, if the network map shows a color alert for a device and the device does not respond to a ping, the State Change Timeline will provide additional information concerning when and how the device went “down”.

The following procedure is applicable for using the State Change Timeline report.

- 1 Select Reports→ Group
 - The **Group Reports** window is displayed. Click on **State Change Timeline** from the listing of Historical Availability reports. A list is displayed describing state change events recorded by monitors for devices during the selected timeframe. **Note:** The default date range is the current day (today). Column headers can be clicked to sort the list by Start Time, Device-Monitor, State, Duration, and Message.
- 2 Review the list of events to identify, for example, when a monitor reported a device as Down.
 - The report provides the date and time of the event and its duration and for Down events, the reason why the event occurred.
 - Click on an entry in the Device-Monitor column to obtain a filtered list containing only the events for the selected device.

- 3 If it is desirable to view events from the prior time period, click on the **Back** icon () , then select a new **<date range>** and click **GO**
 - The activities from the selected time period is displayed.
 - 4 If it is desirable to print the contents of the display, click on the **Print** icon.
 - To print the contents of the display, either select **File -> Print** from the WhatsUp Professional toolbar, or click the **Printer friendly version** icon at the tip-right corner of the report. Clicking the icon opens the report in your system's default web browser for printing.
 - 5 To export the report in text or Excel format, open the Export Report dialog box by clicking the **Export Report** icon. Choose whether to **Export to text** or **Export to Excel** and whether to include the title and/or column names. Also choose a **column delimiter** and a **text qualifier**. Then click **Export**, which displays the File Download dialog box. Here choose whether to **Open** the file, **Save** it, or **Cancel** the export.
-

Whazzup???

A powerful COTS program that has been modified for monitoring the system is EcMsWz - Whazzup. It is a web-accessed program that provides a graphical display of Host Status, Mode Status, Mode Verification and Performance Management. Figure 7 shows the initial Whazzup display.

These functions of Whazzup provide graphical displays of host and software-server status in real-time mode. When used in conjunction with ECS Assistant, System Administrators can acquire a comprehensive knowledge of the system's status.

To start EcMsWz-Whazzup, execute the following procedure:

Starting EcMsWz-Whazzup

- 1 Log in to a host machine.
- 2 At the UNIX prompt on the host from which Whazzup is to be run, type **setenv DISPLAY <hostname>:0.0** press the **Return/Enter** key.
 - **Note:** If the host has been remotely accessed via ssh then do not use the setenv DISPLAY command again. Doing so will compromise system security.
 - **hostname** is the name of the machine on which Whazzup is to be displayed, i.e., the machine you are using.
 - To verify the setting, type **echo \$DISPLAY** then press the **Return/Enter** key.

- 3 At the UNIX prompt, using secure shell, log on to the Whazzup host, xxins0x. Type **ssh xxins0x** then press the **Return/Enter** key.
- 4 Type ***Passphrase*** then press the **Return/Enter** key.
 - You are logged into the Whazzup host machine.
- 5 To start the Netscape web browser type **netscape &** then press the **Return/Enter** key.
 - You are in the web browser on the Whazzup host xxins0x.
- 6 In the **Location** field of the Netscape browser type the URL for Whazzup (e.g., **http://xxins0x:5150**) then press the **Return/Enter** key.
 - The Whazzup intro screen appears (Figure 7).




Figure 7. ECS Whazzup Initial Display

7 Select a monitoring function:

- **Host Status** to determine individual host parameters.
 - **Mode Status** to determine “up” servers for the selected Mode.
 - **Verify Mode** to determine status of all servers for a selected Mode.
 - **Performance Management** to determine the performance status of all hardware/software servers for all modes.
-

Host Status

Selecting Host Status provides a pop-up box (Figure 8) from which to choose a specific host to determine its status.

Host Status data include percent of CPU used, Swap Free space, Memory Free space, and Server information (Figure 9).

Selecting Mode Status (Figure 10) enables a pop-up window showing Modes available. Subsequent to selecting the desired Mode, a display of “up” system servers is provided as shown in Figure 11.

Verify Mode

Selecting **Verify Mode** and choosing a desired mode (Figure 12) will provide a thorough display of system server status, by host, for the mode (Figure 13). Alternatively, selecting **What's Down** will provide a display indicating all down system servers, by mode, by host.

Performance Management

Following recommended monitoring procedures, the optimum method of system monitoring is to select **What's Down** from **Verify Mode** and then **Right Click** on **Performance Management** (Figure 14) and open the link in a new window (Figure 15).

Having these two displays active simultaneously will provide the Systems Administrator the status of “down” system servers and the performance status of individual hosts.

ECS Health Check GUI

The ECS Health Check GUI (Figures 16 and 17) indicates the status of the EcDmV0ToEcsGateway and Data Pool drill-down search engine. At a specified rate it sends inventory searches to the EcDmV0ToEcsGateway and/or submits granule search requests to the Data Pool. It provides warnings by the following means when a failure is registered by the GUI during the current search:

- Visual warning (including details about the time and nature of the error).
- Audible alarm (when implemented).




Figure 8. Host Status Pop-Up Display




Figure 9. Host Status Data Display




Figure 10. Mode Status Pop-Up Display




Figure 11. Mode Status Data Display



Figure 12. Verify Mode Pop-Up Display




Figure 13. Verify Mode Data Display




Figure 14. Performance Management Selection Display




Figure 15. Performance Management Data Display




Figure 16. ECS Health Check GUI at Startup




Figure 17. ECS Health Check GUI Having Detected an Error

- E-mail message.

Starting and Using the ECS Health Check GUI

The ECS Health Check GUI is accessible on the Sun Consolidation Internal Server host. To access the tool and view the current status of the EcDmV0ToEcsGateway and/or Data Pool use the procedure that follows.

Start and Use the ECS Health Check GUI

- 1 Log in to the Sun Consolidation Internal Server host as cmshared.
 - The EcCsHealthCheckStart script must be run by cmshared.
 - Examples of Sun Consolidation Internal Server hosts include **g0acs11**, **e0acs11**, **l0acs03**, and **n0acs04**.
 - For detailed instructions refer to the **Log in to System Hosts** procedure (previous section of this lesson).
- 2 At the UNIX prompt type **cd /usr/ecs/<MODE>/CUSTOM/bin/CSS** and then press the **Return/Enter** key.
 - Change to the directory containing the start script (i.e., EcCsHealthCheckStart) for the ECS Health Check GUI.
 - The location is different from that of most other start scripts because the COTS dependency on the V0ImClientSimulator application requires that the parent application be run in the same directory as the V0ImClientSimulator binary.
- 3 At the UNIX prompt type **EcCsHealthCheckStart <MODE>** and then press the **Return/Enter** key.
 - The ECS Health Check GUI is displayed.
- 4 Click on the appropriate tab for the area to be monitored.
 - The following choices are available:
 - **EcDmV0ToEcsGateway.**
 - **ECS Datapools.**
- 5 In the **Specify timeout period: minutes** and **seconds** text entry boxes type the number of minutes and seconds (respectively) before timeout.
 - **Timeout period** specifies how long the GUI will wait for a response from the current search before flagging an error.

- 6 In the **Specify repeat period: minutes** and **seconds** text entry boxes type the number of minutes and seconds (respectively) before repeating a search.
 - **Repeat period** specifies how often the GUI sends an inventory search to the area being monitored.
- 7 Click on the **Start** button in the **Control** pane to start checking the selected area.
 - The ECS Health Check GUI starts sending inventory searches to the selected area at the frequency specified in the **Specify repeat period** text boxes.
 - **The Current Status is:** (as displayed on the GUI) changes from **Dormant** to **Running**.
- 8 Repeat Steps 4 through 7 to set up inventory searches of the other area (if applicable).
- 9 Observe information displayed in the **Visual Warnings** pane of the ECS Health Check GUI and listen for audible warnings (if enabled).
 - Nothing much will appear to happen unless an error occurs in an inventory search sent to the EcDmV0ToEcsGateway/Data Pool, in which case the following indications will be evident (as shown in Figure 17):
 - **The Current Status is:** (as displayed on the GUI) changes from **Running** to **Failed** (in red).
 - Details concerning the time and nature of the error are displayed in the **Visual Warnings** text pane.
 - The **Mail Warnings** pane indicates that mail has been sent successfully to the recipients in the list.
 - A repeating audible alarm sounds (if enabled).
 - If an error occurs in a search sent to the EcDmV0ToEcsGateway/Data Pool, no further inventory searches will be sent to the selected area unless restarted using the **Start** button in the **Control** pane (refer to Step 13).
 - When an error occurs in an inventory search sent to the EcDmV0ToEcsGateway/Data Pool a detailed, time stamped description of the error is recorded in the EcCsHealthCheck.ALOG file in the /usr/ecs/*MODE*/CUSTOM/logs directory.
- 10 To stop an audible alarm (when applicable) click on the **Stop** button in the **Audible Warnings** pane.
 - The alarm stops sounding.
- 11 To clear error information from the ECS Health Check GUI (when applicable) click on the **Reset** button in the **Control** pane.
 - The error information is cleared from the ECS Health Check GUI.

- 12 To stop inventory searches of the selected area (when applicable) click on the **Stop** button in the **Control** pane.
 - The GUI goes to a Dormant state.
 - 13 To restart inventory searches of the selected area (when applicable) return to Step 7 (click on the **Start** button in the **Control** pane).
 - The GUI goes to a dormant state.
 - 14 To exit from the ECS Health Check GUI (when applicable) select **File → Exit** from the pull-down menu.
 - The ECS Health Check GUI is dismissed.
-

ECS Assistant and ECS Monitor

The Whazzup tool provides a quick look capability to note whether any servers are down. The ECS Assistant and ECS Monitor tools provide additional easy-to-use tools that offer a server monitoring and ping capability (ECS Monitor) as well as a capability to start and stop servers (ECS Assistant). Figure 18 shows the ECS Assistant GUI for access to manager functions, the ECS Assistant subsystem manager GUI, and an example of a confirmation dialog.

Starting ECS Assistant

- 1 Log in to one of the host machines.
- 2 At the UNIX prompt on the host from which the ECS Assistant is to be run, type **setenv ECS_HOME /usr/ecs** then press the **Return/Enter** key.
 - To verify the setting, type **echo \$ECS_HOME** then press the **Return/Enter** key.
- 3 At the UNIX prompt, type **cd /tools/common/ea** then press the **Return/Enter** key. Then type **EcCoAssist /tools/common/ea &** then press the **Return/Enter** key.
 - **/tools/common/ea** is the path where ECS Assistant is installed, and also where EcCoScriptlib may be found.
 - The ECS Assistant GUI is displayed.
- 4 At the ECS Assistant GUI, click the **Subsystem Manager** pushbutton.
 - The Subsystem Manager GUI is displayed.

- 5 Select a mode by clicking on the down arrow at the right end of the **Mode** field and then on the desired mode name in the resulting list.
 - The selected mode is displayed in the **Mode** field and colored indicators show the installation status for components in that mode on the host; the legend for the color indications is at the lower right on the Subsystem Manager window.
- 6 In the list of subsystems, double click on the name of the subsystem of interest.
 - One or more component groups appear below the selected subsystem name.




Figure 18. ECS Assistant GUI Manager Windows

- 7 Double click on the name of a component group.
 - One or more application groups appear below the selected component group name.
- 8 Double click on the name of the application group of interest.
 - The applications or servers in the selected group are listed below the name of the group.
- 9 Single click on the name of an application or server of interest.
 - The selected application or server is highlighted.

- Detailed installation information is displayed in the **Installation Statistics** window.
-

ECS Monitor provides a convenient way to monitor the status of the servers by listing their up/down condition. The ECS Monitor GUI is shown in Figure 19; the status flag for a server is up or down indicating whether or not that server is running, and for a server that is running, the window shows the process ID (PID), the user ID, and the start time. There is a script that works with a *Sweeper* binary to ping the servers and clients in a mode to determine their status.




Figure 19. ECS Monitor GUI

Using the ECS Assistant Server Monitor

- 1 Log in to one of the host machines.
 - 2 At the UNIX prompt on the host from which the ECS Assistant is to be run, type **setenv ECS_HOME /usr/ecs** then press the **Return/Enter** key.
 - To verify the setting, type **echo \$ECS_HOME** then press the **Return/Enter** key.
 - 3 At the UNIX prompt, type **cd /tools/common/ea** then press the **Return/Enter** key.
 - **/tools/common/ea** is the path where ECS Monitor is installed.
 - 4 Type **EcCoMonitorGui /tools/common/ea <MODE> &**, then press **Return/Enter** key.
 - **/tools/common/ea** is the path where EcCoScriptlib may be found.
 - The **ECS Monitor GUI** is displayed, showing the status (**UP** or **DOWN**) of the servers on the current host in the mode specified in the command, as indicated near the top left corner of the window.
 - The status “**UP/DOWN**” indicates whether a listed server is running.
 - 5 To update the **Server Monitor** GUI click the **update** button in the GUI.
 - This causes the list to update to the current status.
 - 6 To monitor other servers, log in to other hosts and launch the ECS Monitor GUI in the desired mode, as in Steps 2 through 4.
 - To exit, click the **EXIT** button. This terminates display of the monitor GUI.
-

Use the following procedure to ping servers.

Using EcCsIdPingServers to Determine Server Status

- 1 Log in to one of the host machines.
- 2 At the UNIX prompt, type **cd /usr/ecs/MODE/CUSTOM/utilities** then press the **Return/Enter** key.
 - The prompt reflects a change to directory **cd /usr/ecs/MODE/CUSTOM/utilities**, where **MODE** is likely to be **OPS**, **TS1**, or **TS2**.
- 3 Then type **EcCsIdPingServers MODE** then press the **Return/Enter** key.
 - The result should appear similar to the following:
**/usr/ecs/DEV03/CUSTOM/bin/CSS/Sweeper -nsh dss2 -nsp 22822
FoSwSweeper application started...**

We made a connection with EntryId =g0icg01:17871:12451240 ---
 EcSrTransportEcInGranServer
 We made a connection with EntryId =g0ins02:22336:6737528 --- DsHrQuitIDL
 We made a connection with EntryId =g0pls02:35211:25637 --- PLOdMsgDObj
 We made a connection with EntryId =g0dis02:48315:18311 ---
 DsDdRequestMgrIDL
 We made a connection with EntryId = g0ins02:17862:12461267 ---
 InAutoIngestIF
 We made a connection with EntryId = g0dis02:49473:13375 --- DsStReqMgrIDL
 We made a connection with EntryId = g0ins02:41566:13071 --- IoAdRpc
 We made a connection with EntryId = g0ins02:18139:12460808 ---
 InRequestMgrIF
 We made a connection with EntryId =g0dms03:42000:13266 ---
 EcSrTransportDDICT
 We made a connection with EntryId = g0pls02:22359:6737528 ---
 DsHrNonConfIDL681ab65e-60bc-1024-8e70-08006902a6d6
 We made a connection with EntryId = g0pls02:22346:6737528 ---
 DsHrConformantIDL681ab65d-60bc-1024-8e70-08006902a6d6
 We made a connection with EntryId =g0mss21:64657:8006 --- EcAcOrderMgr
 We made a connection with EntryId =g0mss11:41449:22898 ---
 EcSrTransportDarServer
 We made a connection with EntryId = g0icg02:17724:12445092 --- EcRgRegistry
 We made a connection with EntryId =g0mss11:41278:22739 ---
 InDDNTransferPkt
 We made a connection with EntryId =g0psl02:35085:25466 --- Deletion
 We made a connection with EntryId =g0pls02:35168:25584 ---
 SubscriptionQueue
 We made a connection with EntryId =g0mss21:64700:8059 ---
 MsAcUsrRequestMgr
 We made a connection with EntryId =g0mss21:64690:8059 ---
 MsAcRegUserMgr
 We made a connection with EntryId =g0mss21:64695:8059 ---
 MsAcUsrProfileMgr
 We made a connection with EntryId =g0pls02:35127:25527 ---
 DpPrSchedulerDObj
 We made a connection with EntryId =g0ins02:22364:6738409 ---
 DsHrNonConfIDL681ab654-60bc-1024-8e70-08006902a6d6
 We made a connection with EntryId =g0ins02:22353:6738409 ---
 DsHrConformantIDL681ab653-60bc-1024-8e70-08006902a6d6
 We made a connection with EntryId =g0ins02:22342:6738409 --- DsHrQuitIDL

Tape Operations

In this lesson you will learn how Networker Administrative software and the Exabyte tape drive work together to administer the use of tapes for system backups and file restorations. Functions such as how to label a new tape, how to index a tape cartridge, and how to perform backups and restores are covered.

Terms:

- **Cartridge** - A hardware device that is part of the Exabyte tape drive. It holds up to 10 tapes that are automatically selected by Networker.
- **Drive** - Hardware device into which the tape or tape cartridge is inserted that performs the actual recording of data.
- **Index** - A list of the labeled tapes currently stored in the jukebox.
- **Inventory** - The action of making an index.
- **Jukebox** - A hardware device that stores more than one tape used for system backups and restores. Working in conjunction with specialized software, it can automatically select the proper tape, load the tape into the tape drive, and return it to its appropriate slot upon completion of the task.
- **Label** - A unique name assigned to a tape by Networker.
- **Volume** - A recording medium; in the case of this course, a volume and a tape are synonymous.

Networker Administrator Screen

The main Networker Administrator screen (Figure 20), which is displayed after typing **nwadmin** at a UNIX prompt, contains four main sections:

- The menu bar at the top of the screen, which displays all of the possible capabilities of Networker Admin.
- The **speedbar**, which can be customized, displays icons that execute the most common procedures.
- Current configuration information, including the current Networker server, the available backup devices (tape drives, file systems, CD-ROMs, etc.).
- Current status windows, which display in real time the actual activity on the various devices, and progress and error messages.




Figure 20. NetWorker Administrative Main Screen

Labeling Tapes

Files and directories have unique names that are assigned by the user to identify them. In much the same manner, tapes are given unique names, or labels. This allows such programs as NetWorker and such hardware devices such as the Exabyte jukebox to automate the tape selection process when performing system backups and restores. When a tape is initialized, NetWorker assigns it a label. NetWorker then stores the tape's label with a file that is written to

the tape so that when a file restoration request is received, Networker will know exactly which tape to select from the jukebox.

Performing Tape Labeling

- 1 Log in to a system terminal.
- 2 To set the display to the current terminal type **setenv DISPLAY <IPNumber>:0.0** then press the **Return/Enter** key.
- 3 To start the log-in to the Backup client server type **ssh BackupServerName** in the second window and then press the **Return/Enter** key.
 - If you have previously set up a secure shell passphrase and executed **ssr (sshremote)**, a prompt to **Enter Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase, go to Step 4.
- 4 If a prompt to **Enter Passphrase for key '<user@localhost>'** appears, type your **Passphrase** and then press the **Return/Enter** key. Go to Step 5.
- 5 At the **<user@remotehost>'s password:** prompt, type your **Password** and then press the **Return/Enter** key.
- 6 To start the log-in as root type **su** then press the **Return/Enter** key.
 - A password prompt is displayed.
- 7 At the password prompt enter **RootPassword** then press the **Return/Enter** key.
 - Remember that the password is case sensitive.
 - You are authenticated and returned to the UNIX prompt.
- 8 At the UNIX prompt, type **nwadmin** then press the **Return/Enter** key.
 - A window opens for the Networker Administrative program.
- 9 Insert the blank tape(s) in the jukebox's cartridge.
 - Remove any non-blank tapes from the cartridge or else they will be re-labeled and the data on the tapes will be lost.
- 10 Install the cartridge in the jukebox.
- 11 Click the **Label** button.
 - The **Jukebox Labeling** window opens (Figure 21).




Figure 21. Jukebox Labeling Window

- 12 In the field marked **Starting with**, type the tape label you wish to use for the first tape in the sequence.
- Tape labels are named by using the host name (e.g., **x0acg01**), a dot or period, and a sequential number (e.g., **001**, **002**).
 - By default, the system will prompt you with the next label in the sequence (e.g., **x0acg01.011**).

- 13 In the **First Slot** field, enter **1** or the slot containing the first volume to be labeled; in the **Last Slot** field, enter **10** or the slot containing the last volume to be labeled.
 - Slot 1 is at the top of the cartridge and 10 at the bottom.
 - Slot 11 is the non-removable slot within the jukebox. This usually contains a cleaning tape.
 - It is OK to leave empty slots.
 - 14 Click on the **OK** button.
 - A status message indicating the progress of the tape labeling procedure appears and updates.
 - Labeling a full cartridge of tapes takes about 15 minutes.
 - 15 When the status in the **Jukebox Labeling** window reads **finished**, click on the **Cancel** button.
 - The **Jukebox Labeling** window closes.
 - 16 Select **File → Exit** from the pull-down menu.
 - The **nwadmin** program terminates and you are returned to the UNIX prompt.
 - 17 At the UNIX prompt for the backup server, type **exit** then press the **Return/Enter** key.
 - **Root** is logged out.
 - 18 Type **exit** again then press the **Return/Enter** key.
 - You are logged out of and disconnected from the backup server.
 - 19 Put an identifying sticker on the outside of each tape cassette.
-

Indexing Tapes

Labeled tapes are loaded in a tape cartridge that is inserted into the Exabyte tape drive, also referred to as the jukebox. Networker needs to know the location of each tape in the jukebox. To do this, Networker uses a process called **inventory**, which prepares an index by matching a tape label to the cartridge slot that holds that tape (Figure 22). Then, when a request to recover a file or a set of files is received, *Networker* locates the tape based on the information in its memory.

CAUTION

If you move a tape from its position in the cartridge, Networker will not know where to find it (Figure 23). You must re-index the cartridge by performing these procedures again for Networker to select the correct tape (Figure 24).




Figure 22. Tape Index Following the Initial Inventory




Figure 23. Tapes Changed But Not Re-Inventoried




Figure 24. Index is Updated after Re-Inventory

Indexing Tape

- 1 Login to a system terminal.
- 2 Set display to current terminal by typing: **setenv DISPLAY <IPNumber>:0.0** then press the **Return/Enter** key.
- 3 Start the log-in to the Backup client server by typing **ssh BackupServerName** in the second window and then press the **Return/Enter** key.
 - If you have previously set up a secure shell passphrase and executed **sshremote**, a prompt to **Enter Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase, go to Step 4.
- 4 If a prompt to **Enter Passphrase for key '<user@localhost>'** appears, type your **Passphrase** and then press the **Return/Enter** key. Go to Step 5.
- 5 At the **<user@remotehost>'s password:** prompt, type your **Password** and then press the **Return/Enter** key.
- 6 Log in as root by typing **su** then press the **Return/Enter** key.
 - A password prompt is displayed.

- 7 Enter the **RootPassword** then press the **Return/Enter** key.
 - You are authenticated as root and returned to the UNIX prompt.
- 8 At the UNIX prompt, type **nwadmin** then press the **Return/Enter** key.
 - A window opens for the **Networker Administrative** program.
- 9 Click the **Mount** button, or select **Media -> Mount** from the menu.
 - The **Jukebox Mounting** window opens (Figure 25) and displays a list of the tapes that Networker is currently aware of.
 - When you are finished with this window, click the **Cancel** button.




Figure 25. Jukebox Mounting Window

- 10 Insert the required tape(s) in the jukebox's cartridge then install the cartridge in the jukebox.
 - Refer to the jukebox's documentation for detailed instructions on installing the cartridge.
 - 11 Select **Media** from the menu bar then select **Inventory**.
 - The **Jukebox Inventory** window opens.
 - 12 In the **First Slot** field, enter **1** or the slot containing the first volume to be labeled; in the **Last Slot** field, enter **10** or the slot containing the last volume to be labeled.
 - Slot 1 is at the top of the cartridge and 10 at the bottom.
 - Slot 11 is the non-removable slot within the jukebox. This usually contains a cleaning tape.
 - It is OK to leave empty slots or slots with previously inventoried tapes.
 - 13 Click the **OK** button.
 - A status message indicating the progress of the tape indexing procedure appears and updates.
 - Inventorying a full cartridge of tapes takes between 20 and 30 minutes.
 - 14 When the **Jukebox Inventory** status reads **finished**, click the **Cancel** button.
 - 15 Click the **Mount** button to verify that the indexing worked.
 - The **Jukebox Mounting** window opens.
 - The **required tape(s)** should be shown. If not, repeat this procedure from Step 9.
 - 16 Click the **Cancel** button.
 - The **Jukebox Mounting** window closes.
 - 17 From the menu bar, select **File** then select **Exit**.
 - 18 At the UNIX prompt for the *BackupServer*, type **exit** then press the **Return/Enter** key.
 - 19 At the next UNIX prompt type **exit** again then press the **Return/Enter** key.
-

This page intentionally left blank.

System Backups and Restores

Performing regular and comprehensive backups is one of the most important responsibilities a System Administrator has. Backups are the insurance that essentially all of the system data is always available. If the system crashes and all disks are damaged, the System Administrator should be able to restore the data from the backup tapes depending on backup method (e.g., full or partial).

Incremental Backup

An incremental backup copies to tape all files on a system or subsystem that were created or modified since the previous incremental backup regardless of the backup level. The purpose of an incremental backup is to insure that the most recent edition of a file is readily available in case user error or disastrous system failure causes the file to become corrupt. Incremental backups are scheduled at a time that causes minimal disruption to the users. Copies of all incremental backup tapes are stored offsite for five weeks before they are reused.

Incremental backups are performed automatically according to the schedule setup in the Networker. Schedules windows (Figure 26). Incremental backups can also be requested at unscheduled times by completing the **Incremental Backup Request Form** and submitting it to the DAAC manager.

Performing On-Demand Incremental Backup

- 1 Log in to a system terminal.
- 2 To set the display to the current terminal type **setenv DISPLAY <IPNumber>:0.0** then press the **Return/Enter** key.
- 3 To start the log-in to the Backup client server type **ssh BackedUpSystemName** in the second window and then press the **Return/Enter** key.
 - If you have previously set up a secure shell passphrase and executed **sshremote**, a prompt to **Enter Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase, go to Step 4.
- 4 If a prompt to **Enter Passphrase for key '<user@localhost>'** appears, type your **Passphrase** and then press the **Return/Enter** key. Go to Step 5.
- 5 At the **<user@remotehost>'s password:** prompt, type your **Password** and then press the **Return/Enter** key.




Figure 26. Networker Schedules Window

- 6 Log in as root by typing **su** then press the **Return/Enter** key.
 - A password prompt is displayed.
- 7 Enter the **RootPassword** then press the **Return/Enter** key.
 - You are authenticated as root and returned to the UNIX prompt.
- 8 At the UNIX prompt, type **nwadmin** then press the **Return/Enter** key.
 - A window opens for the Networker Administrative program.
- 9 Select **Customize → Schedules** from the pull-down menu.
 - The **Schedules** window opens.

- 10 Look at the button for today and note the letter on that day. If there is an **i** next to the date on this button, go to Step 11.
 - The **i** stands for incremental; **f** stands for full. Whichever is on the button for today is what kind of backup that will be done, unless it is overridden.
- 11 Click and hold the button for today, select **Overrides** from the resulting menu, select **Incremental** from the next resulting menu.
- 12 Click on the **Apply** button.
- 13 Close the **Schedules** window by clicking in the upper left corner of the **Schedules** window and selecting **Close** from the resulting menu.
- 14 Click the **Group Control** button.
 - The **Group Control** window opens.
- 15 Click on the **Start** button.
 - A **Notice** window opens.
- 16 Click on the **OK** button.
 - The **Notice** window closes. The regularly scheduled backup will still run (even though we are now doing a backup).
- 17 Close the **Group Control** window by clicking in the upper left corner of the **Group Control** window and selecting **Close** from the resulting menu.
 - Status updates appear in the **nwadmin** window.
 - When the backup is complete, a **Finished** message will appear.
- 18 If the button for today in Step 10 had an **i** on it, go to Step 22.
- 19 Select **Customize → Schedules** from the pull-down menu.
 - The **Schedules** window opens.
- 20 Click and hold the button for today, select **Overrides** from the resulting menu, and select **Full** from the next resulting menu.
- 21 Click on the **Apply** button.
- 22 Close the **Schedules** window by clicking in the upper left corner of the **Schedules** window and selecting **Close** from the resulting menu.
- 23 To quit the Networker Administrative program select **File → Exit** from the pull-down menu.
 - The **nwadmin** window closes.

- 24 At the UNIX prompt for the machine to be backed up, type **exit** then press the **Return/Enter** key.
 - Root is logged out.
 - 25 Type **exit** again then press the **Return/Enter** key.
 - You are logged out and disconnected from the machine to be backed up.
-

Full System Backup

A full system backup is a snapshot of the data on the entire system as of a particular date. The data is stored on tapes that are used to recreate the system in the event of a total system failure. The full system backup is run by the System Administrator on a regular schedule, usually weekly. Full system backup tapes are stored offsite for security reasons.

Performing Full Backup

- 1 Log in to a system terminal.
- 2 To set the display to the current terminal type **setenv DISPLAY <IPNumber>:0.0** then press the **Return/Enter** key.
- 3 To log in to the machine to be backed up type **ssh BackedUpSystemName** then press the **Return/Enter** key.
 - If you have previously set up a secure shell passphrase and executed **sshremote**, a prompt to **Enter Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase go to Step 4.
- 4 If a prompt to **Enter Passphrase for key '<user@localhost>'** appears, type your **Passphrase** and then press the **Return/Enter** key. Go to Step 5.
- 5 At the **<user@remotehost>'s password:** prompt, type your **Password** and then press the **Return/Enter** key.
- 6 To log in as root type **su** then press the **Return/Enter** key.
 - A password prompt is displayed.
- 7 Type the **RootPassword** then press the **Return/Enter** key.
 - You are authenticated as root and returned to the UNIX prompt.




Figure 27. Networker Backup Window

- 8 To execute the Networker Backup program type **nwbackup** then press the **Return/Enter** key.
 - A Networker Backup window opens (Figure 27). You are now able to perform a full backup.
- 9 If no **files/directories to be backed up** were provided by the requester, i.e. the whole machine is to be backed up, then type / in the **Selection** field and click the **Mark** button.
 - / is designated for backup and has a check next to it.

- 10 If **files/directories to be backed up** were provided, then select the **files/directories to be backed up** in the directory display and click the **Mark** button.
 - Drag scroll bar with the mouse to scroll the list up and down.
 - Double-click on directory name to list its contents.
 - To move up a directory level, type the path in the **Selection** field.
 - Clicking the **Mark** button designates the file for backup and puts a check next to it.
 - 11 Click on the **Start** button.
 - A **Backup Options** window opens.
 - 12 Click on the **OK** button.
 - The **Backup Options** window closes.
 - The **Backup Status** window opens providing updates on the backup's progress.
 - 13 After the **Backup Completion Time** message appears in the **Backup Status** window, click the **Cancel** button.
 - The **Backup Status** window closes.
 - The backup is complete.
 - 14 To quit the Networker Backup program select **File** → **Exit** from the pull-down menu.
 - The Networker Backup window closes.
 - 15 At the UNIX prompt for the **machine to be backed up**, type **exit** then press the **Return/Enter** key.
 - Root is logged out.
 - 16 Type **exit** again then press the **Return/Enter** key.
 - You are logged out and disconnected from the machine to be backed up.
-

Single or Multiple File Restore

From time to time individual files or groups of files (but not all files) will have to be restored from an incremental backup tape due to operator error or system failure.

In order to perform the procedure, the System Administrator must have obtained the following information from the requester:

- Name of machine to be restored.
- Name of file(s) to be restored.

- Date from which to restore.
- User ID of the owner of the file(s) to be restored.
- Choice of action to take when conflicts occur. Choices are:
 - Rename current file
 - Keep current file
 - Write over current file with recovered file

Performing Single or Multiple File Restore

- 1 Log in to a system terminal.
- 2 To set the display to the current terminal type **setenv DISPLAY <IPNumber>:0.0** then press the **Return/Enter** key.
- 3 To log in to the machine to be restored type **ssh <host name> *Machine Restored*** then press the **Return/Enter** key.
 - If you have previously set up a secure shell passphrase and executed **sshremote**, a prompt to **Enter Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase, go to Step 4.
- 4 If a prompt to **Enter Passphrase for key '<user@localhost>'** appears, type your **Passphrase** and then press the **Return/Enter** key. Go to Step 5.
- 5 At the **<user@remotehost>'s password:** prompt, type your **Password** and then press the **Return/Enter** key.
- 6 To log in as root type **su** then press the **Return/Enter** key.
 - A password prompt is displayed.
- 7 Type the **RootPassword** then press the **Return/Enter** key.
 - You are authenticated as root and returned to the UNIX prompt.
- 8 To log in as the user type **su UserID**.
 - You are authenticated as the owner of the file(s) to be restored.
- 9 To execute the Networker Recovery program type **nwrecover** then press the **Return/Enter** key.
 - A window opens for the **Networker Recovery** program (Figure 28). You are now able to restore files.




Figure 28. Networker Recovery Window

- 10 Select **file(s) to be restored** and click the **Mark** button.
 - Drag scroll bar with the mouse to scroll the list up and down.
 - Double-click on directory name to list its contents.
 - Clicking on the **Mark** button designates the file for restore and puts a check next to it.
- 11 Select **Change → Browse Time** from the pull-down menu.
 - The **Change Browse Time** window opens.
- 12 Select the **date from which to restore**.
 - Networker will automatically go to that day's or a previous day's backup which contains the file.
- 13 Click on the **Start** button.
 - The **Conflict Resolution** window opens.
- 14 In response to the question "Do you want to be consulted for conflicts" click on the **yes** button.
- 15 Click on the **OK** button.
 - If prompted with a conflict, choices of action will be: rename current file, keep current file, or write over current file with recovered file.
 - Select the requester's **choice of action to take when conflicts occur**.
 - The **Recover Status** window opens providing information about the to be restored.
 - If all the required tapes are not in the drive, a notice will appear.
 - Click on the **OK** button in the notice window.
- 16 When a **recovery complete** message appears, click on the **Cancel** button.
- 17 Select **File → Exit** from the pull-down menu.
 - The Networker Recovery program quits.
- 18 Type **exit** then press the **Return/Enter** key.
 - The owner of the file(s) to be restored is logged out.
- 19 Type **exit** again then press the **Return/Enter** key.
 - Root is logged out

20 Type **exit** one last time then press the **Return/Enter** key.

- You are logged out and disconnected from the **machine to be restored**.
-

Complete System Restore

A complete system restore is an emergency procedure that should be performed only in the event of a system crash with the loss of data. The only way to get the system back up and running in a timely fashion is to restore the system from a previous backup. The result of this action will be that any updates to the system between the last backup and the time of the restore will be lost. The System Administrator will determine which complete backup tape(s) to use (Figure 29). Depending on the frequency of complete system backups and incremental backups, data loss can be minimized.




Figure 29. Tapes Required for Full System Restore

A complete system restore involves restoring a number of tapes depending upon the particular situation. For example, should a system failure occur immediately after a full system backup was performed, only the tapes used in that backup will be required to restore the system to its usable state. However, if there was a period of time between the last full system backup and the system failure, tapes from the last full system backup as well as partial and incremental backups will have to be restored. This may become a time consuming process depending on the server affected, how much data is to be recovered, and how many tapes need to be restored. Additionally, the System Administrator may determine that only one or two of the many

partitions need to be restored to make the system whole again. Therefore, these procedures will have to be mixed and matched to determine the proper restoration procedure for a given situation.

To perform the procedure, the SA must have the following information about the requester:

- Name of system to be restored
- Date from which to restore

Performing Full System Restore

- 1 To log in to the backup server type `/tools/bin/ssh BackupServerName` then press the **Return/Enter** key.
- 2 To set the display to the current terminal type `setenv DISPLAY <IPNumber>:0.0` then press the **Return/Enter** key.
- 3 To log in to the machine to be restored type `/tools/bin/ssh MachineToRestore` then press the **Return/Enter** key.
 - If you have previously set up a secure shell passphrase and executed **ssr**, a prompt to **Enter Passphrase for key '<user@localhost>'** appears; continue with Step 3.
 - If you have not previously set up a secure shell passphrase, go to Step 4.
- 4 If a prompt to **Enter Passphrase for key '<user@localhost>'** appears, type your *Passphrase* and then press the **Return/Enter** key. Go to Step 5.
- 5 At the *<user@remotehost>*'s **password:** prompt, type your *Password* and then press the **Return/Enter** key.
- 6 To log in as root type `su` then press the **Return/Enter** key.
 - A password prompt is displayed.
- 7 Type the *RootPassword* then press the **Return/Enter** key.
 - You are authenticated as root and returned to the UNIX prompt.
- 8 To set the display to the current terminal type `setenv DISPLAY <IPNumber>:0.0` or `setenv DISPLAY BackupServerName:0.0` then press the **Return/Enter** key.
- 9 To log in as the user type: `su UserID` then press the **Return/Enter** key.
 - You are authenticated as the owner of the file(s) to be restored.
- 10 To set the display to the current terminal type `setenv DISPLAY IPNumber:0.0` or `setenv DISPLAY MachineRestored:0.0` then press the **Return/Enter** key.

11 To execute the Networker Administrator program type **nwadmin** then press the **Return/Enter** key.

- A window opens for the Networker Administrator program (Figure 30).
- You are now able to perform restores of partitions.




Figure 30. Networker Administrator's Window

- 12 Select **Save Set → Recover Set** from the pull-down menu.
 - The **Save Set Recover** window opens.
- 13 Select the **Name of system to be restored** (referred to as **System** in the rest of this procedure) in the **Client** field's menu.
 - The **Save Set** listing updates. This is a listing of partitions on the **System**.
 - At this time, note the partitions listed for the **System**. To do a complete system restore, this procedure needs to be performed for each partition listed.
- 14 Select the **Save Set**/partition from the listing.
 - The **Instance** listing updates.
- 15 Select the appropriate **Instance**.
 - An **Instance** is a particular Networker client backup. A listing of **Instances** is a report detailing the Networker client backups that have occurred.
 - Select an **Instance** based upon the **Date from which to restore** (referred to as **Date** in the rest of this procedure) and of an appropriate level:
 - To determine a base **Date**, you must consider the time of day that backups occur. For example, if the backup occurs at 02:00 each morning then a system corrupted at noon on June 6 would require a restoration of the June 6 backup. However, if the system corruption took place around the time of the backup, it would be more prudent to use the backup from June 5.
 - If the backups are full or incremental, perform the following actions:
 - Select the most recent full backup that occurred on or prior to the **Date** and perform a partition restore. If the date of this full backup is not the same as the **Date**, perform a partition restore using each incremental backup, in chronological order, between this full backup and the day after the **Date**.
 - If the backups are of different numerical levels, follow these steps:
 - First select the most recent level 0/full backup prior to or on the **Date** and perform a restore of the partition. If a level 0/full backup did not occur on the **Date**, select the most recent backup of the next highest level occurring after this level 0 and prior to or on the **Date**.
 - Perform a restore of the partition. Continue to select the most recent backup of the next highest level occurring between the last used **Instance** and the day after the **Date** until reaching an instance on the **Date**.
 - You can double click an **Instance** to see which tape is required.
- 16 Click on the **Recover** button.
 - The **Save Set Recover Status** window opens.

- To show which tapes are required click on the **Volumes** button.
- 17 Click on the **Options** button.
- The **Save Set Recover Options** window opens.
- 18 Set Duplicate file resolution to Overwrite the existing file by clicking its radio button.
- 19 Make sure that the **Always prompt** checkbox is **not** checked.
- 20 Click on the **OK** button.
- The **Save Set Recover Options** window closes.
- 21 Click on the **Start** button in the **Save Set Recover Status** window.
- Status messages appear in the **Status** box.
 - A **recovery complete** message appears when recovery is complete.
- 22 Click on the **Cancel** button after the **recovery complete** message appears.
- The **Save Set Recover Status** window closes.
- 23 If additional partition restores are required, go to Step 12. Otherwise, select **File → Exit** from the pull-down menu to quit the Networker Administrator program.
- 24 At the UNIX prompt for the backup server, type **exit** then press the **Return/Enter** key.
- 25 Type **exit** again then press the **Return/Enter** key.
-

User Administration

Screening Personnel

Screening Criteria

Some positions require special access privileges in order to do the assigned job or duties. These are called public trust positions because they can affect the integrity, efficiency, or effectiveness of the system to which they have been granted privileged access. Screening for suitability, prior to being granted access, is required. This screening, National Agency Check (NAC), is required to ensure that granting any special access privileges to someone would not cause undue risk to the system for which that employee has these privileges. Line Management is responsible for requesting suitability screening for the employees in their respective organizations.

OMB Circular A-130, Appendix III and NPR 2810.1 require the following employees to undergo personnel screening:

- All employees who require privileged access or limited privileged access to a Federal computer system or network.
- Privileged access – Can bypass, modify, or disable the technical or operational system security controls.
- Limited privileged access – Can bypass, modify or disable security controls for part of a system or application but not the entire system or application.

Internet Protocol Operational Network (IONet) Access Protection Policy and Requirements (290-004) requires the following employees to undergo suitability screening:

- All employees who require privileged access, limited privileged access, or access to the Closed Segment of the Internet Protocol Operational Network (IONet) (formerly NASCOM).
- All employees having access to IONet network control devices.

NPR 1600.1 requires that all employees granted unescorted access to a NASA Resource Protection (NRP) facility or area and/or a NASA-designated Limited Area undergo screening.

Screening Procedures

The line manager will submit NASA Form 531 containing the following information for each employee needing suitability screening.

- Full name (first, middle initial and last)
- Goddard badge number if badged employee

- Reason for requesting screening
- Type and date of any previous security investigation or clearance if known
- Phone number and email address

The request should be sent to the EDF Security Administrator. The GSFC Security Office (GSO) will search the personnel security database to determine if a current NAC has been performed. If not the employee will be contacted to obtain additional information. The GSO will report a favorable or unfavorable result back to the EDF Security Administrator upon completion of the suitability screening.

Adding a New User

Adding a user to the system is accomplished through a series of steps that may be performed as a suite from the command line or by use of a script. The procedure below outlines the individual steps that are required to completely set up a new user on the system. The scripts will accomplish these steps in an interactive manner.

The requester fills out a User Registration Request Form and submits it to the requestor's supervisor. The requester's supervisor reviews the request, and if s/he determines that it is appropriate for the requester to have an account, forwards the request to the System Administrator. If the requester requires a National Agency Check (NAC) before access is granted, the supervisor will forward the request to the Security System Engineer, who will then ensure that proper procedures are followed before the request is sent to the System Administrator (SA). The System Administrator verifies that all required information is contained on the form. If it is, s/he forwards the request to the approval authority, the DAAC Manager. Incomplete forms are returned to the requester's supervisor for additional information. If the request for the accounts fits within policy guidelines, the DAAC Manager approves the request and returns the request form to the System Administrator to implement.

The System Administrator should be familiar with a UNIX text editor and the files **/etc/passwd.y** (Figure 31), **/etc/group** (Figure 32), and **/etc/auto.home**.

The System Administrator (SA) creates a new user account with command-line/script entries. As an example, The Goddard Space Flight Center DAAC uses a script, *Newuser*, to add new users to the system. The script, which is available to other DAACs, walks the System Administrator through data input of user information, checks for the same user in other systems, creates a User ID, synchronizes password files and creates home directories for new users.

Deleting a User

The Deleting a User process begins when the requester has determined that no useful files remain in the user's home directory and submits a request to delete the user's account to his/her supervisor. The supervisor approves or denies the request. Once approved, the request is forwarded to the OPS Super. The OPS Super reviews the request and forwards it to the SA who deletes the user's account. When the user has been deleted, the SA notifies the requester, supervisor and OPS Super.




Figure 31. `/etc/passwd.yp` File Fields




Figure 32. `/etc/group` File

Detailed procedures for tasks performed by the SA are provided in the sections that follow.

The procedures assume that the requester's application for deleting a user has already been approved by DAAC Management. In order to perform the procedure, the SA must have obtained the following information from the requester:

- **UNIX login of the user to be deleted**
- **Role(s) of the user to be deleted**

The System Administrator deletes a user with command-line/script entries. As an example, The Goddard Space Flight Center DAAC uses a script, *Lockdown*, to lock, unlock and delete user accounts. This script, which is available to other DAACs, walks the System Administrator through the steps necessary to delete a user account. It assists the System Administrator in locating the correct user account for deletion and deletes the user account and all associated file references. It also enables the System Administrator to lock or unlock accounts.

Changing a User's Account Configuration

Account configuration is accomplished through command line and script. The DAAC manager must authorize changes to user accounts.

The Changing a User Account Configuration process begins when the requester submits a request to the OPS Super detailing what to change about the account configuration and the reason for the change. Requests for changes to privileged accounts shall be sent to the Security System Engineer. The OPS Supervisor or the Security System Engineer reviews the request and forwards it to SA who changes the user's account configuration. When the changes are complete the SA notifies the requester and OPS Supervisor.

In order to perform the procedure, the System Administrator must have obtained the following information from the requester:

- What to change and new settings. Can be any of:
 - New Real User Name
 - New Office Number
 - New Office Phone Number
 - New Home Phone Number
 - New UNIX Group
 - New Login Shell
- Current UNIX Login of the User

Changing User Access Privileges

The Changing User Access Privileges process begins when the requester submits a request to his/her supervisor. Requests for changes to privileged accounts shall be sent to the Security

System Engineer. The supervisor or the Security System Engineer approves or denies the request. Once approved, the request is forwarded to the OPS Super. The Ops Super reviews the request and forwards it to the SA who changes the user's access privileges. When the changes are complete the SA notifies the requester, supervisor and Ops Super.

In order to perform the procedure, the System Administrator must have obtained the following information about the requester:

- Role(s) to which the user is to be added
- Role(s) from which the user is to be removed
- UNIX login of the user

Changing a User Password

The Changing a Users Password process begins when the requester submits a request to the SA. The System Administrator verifies that the requester is who s/he claims to be. Once verified, the SA changes the user's password. When the change is complete the SA notifies the requester.

Detailed procedures for tasks performed by the SA are provided in the sections that follow.

The procedures assume that the requester's application for changing a user password has already been approved by DAAC Management. In order to perform the procedure, the SA must have obtained the following information about the requester:

- UNIX login of the user
- New password for the user

To change a user password for the requester, execute the command line or script procedure steps that have been developed.

Checking a File/Directory Access Privilege Status

Checking File/Directory Access Privileges

- 1 At a UNIX prompt, type **cd *Path*** then press the **Return/Enter** key.
 - The ***Path*** is the full path up to but not including the file/directory on which access privilege status is needed. For example, if the requester wants access privileges status on directory /home/jdoe, type **cd /home** then press the **Return/Enter** key.

- 2 From the UNIX prompt, type **ls -la**. The output from the command should appear as follows:

drwxrwxrwx	3	mresnick	training	8192	Jun 14 08:34	archive
drwxr-xr-x	11	mresnick	training	4096	Jul 03 12:42	daacdata
-rw-rw-rw-	1	mresnick	training	251	Jan 02 1996	garbage
lrw-r--r--	2	jjones	admin	15237	Apr 30 20:07	junk
-rwxr--rw-	1	mresnick	training	5103	Oct 22 1994	trash

- The first column of output is the file access permission level for the file (see Figure 33 below for a description of file permissions).
 - The next column to the right is the number of links to other files or directories.
 - The third column is the file owner's user ID
 - The fourth column is the group membership of that owner.
 - The fifth column shows file size in bytes.
 - The sixth column displays the date and time of last modification (if the date is more than six months old, the time changes to the year)
 - The last column displays the file name.
-

Changing a File/Directory Access Privilege

File and directory access privileges are displayed in the first output column of the **ls -l** command and consist of ten characters, known as **bits**. Each bit refers to a specific permission. The permissions are divided into four groupings shown and briefly described in Figure 33.

In order to perform the procedure, the System Administrator must have obtained the following information about the requester:

- Full path of the file/directory on which access privileges will be changed.
- New access privileges to set on the file/directory. Can be any of:
 - New owner
 - New group
 - New user/owner privileges (read, write and/or execute)
 - New group privileges (read, write and/or execute)
 - New other privileges (read, write and/or execute)




Figure 33. Access Permissions

Changing a File/Directory Access Privilege

- 1 At the UNIX prompt type **su** then press the **Return/Enter** key.
- 2 At the **Password** prompt, type **RootPassword** then press the **Return/Enter** key.
 - Remember that **RootPassword** is case sensitive.
 - You are authenticated as root.
- 3 Type **cd Path** then press the **Return/Enter** key.
 - The **Path** is the full path up to but not including the file/directory on which access privileges will be changed. For example, if the requester wants access privileges changed on directory /home/jdoe type **cd /home** then press the **Return/Enter** key.

- 4 If there is a **New owner** then type **chown *NewOwner FileOrDirectoryName*** then press the **Return/Enter** key.
- The ***FileOrDirectoryName*** is the name of the file/directory on which access privileges will be changed minus the path. For example, if the requester wants access privileges changed on directory /home/jdoe type **chown *NewOwner jdoe*** then press the **Return/Enter** key.
- 5 If there is a **New group** then type **chgrp *NewGroup FileOrDirectoryName*** then press the **Return/Enter** key.
- The ***FileOrDirectoryName*** is the name of the file/directory on which access privileges will be changed minus the path. For example, if the requester wants access privileges changed on directory /home/jdoe type **chgrp *NewGroup jdoe*** then press the **Return/Enter** key.
- 6 If there are **New user/owner privileges** type **chmod *u=NewUserPrivileges FileOrDirectoryName*** then press the **Return/Enter** key.
- The ***FileOrDirectoryName*** is the name of the file/directory on which access privileges will be changed minus the path. For example, if the requester wants access privileges changed on directory /home/jdoe type **chmod *u=NewUserPrivileges jdoe*** then press the **Return/Enter** key.
 - The ***NewUserPrivileges*** are “r” for read, “w” for write, and “x” for execute. For example, to give the user/owner read, write and execute privileges, type **chmod *u=rwx FileOrDirectoryName*** then press the **Return/Enter** key.
- 7 If there are **New group privileges** type **chmod *g=NewGroupPrivileges FileOrDirectoryName*** then press the **Return/Enter** key.
- The ***FileOrDirectoryName*** is the name of the file/directory on which access privileges will be changed minus the path. For example, if the requester wants access privileges changed on directory /home/jdoe type **chmod *g=NewGroupPrivileges jdoe*** then press the **Return/Enter** key.
 - The ***NewGroupPrivileges*** are “r” for read, “w” for write, and “x” for execute. For example, to give the group read and execute privileges, type **chmod *g=rx FileOrDirectoryName*** then press the **Return/Enter** key.
- 8 If there are **New other privileges** then type **chmod *o=NewOtherPrivileges FileOrDirectoryName*** then press the **Return/Enter** key.
- The ***FileOrDirectoryName*** is the name of the file/directory on which access privileges will be changed minus the path. For example, if the requester wants access privileges changed on directory /home/jdoe type **chmod *o=NewOtherPrivileges jdoe***, then press the **Return/Enter** key.

- The *NewOtherPrivileges* are “r” for read, “w” for write, and “x” for execute. For example, to give others read privileges, type **chmod o=r *FileOrDirectoryName*** then press the **Return/Enter** key.

9 Type **exit** then press the **Return/Enter** key.

- Root is logged out.
-

Moving a User's Home Directory

The process of moving a user's home directory begins when the requester submits a request to the Ops Supervisor. The Ops Supervisor approves or denies the request. Once approved, the request is forwarded to the SA who moves the user's home directory. When the changes are complete the SA notifies the requester and Ops Supervisor.

This page intentionally left blank.

Commercial Off-the-Shelf (COTS) Software Administration

The EMD organization provides maintenance for EMD hardware, software, and firmware systems delivered under the EMD contract to the EMD sites.

Commercial off-the-shelf (COTS) software and hardware are maintained in accordance with the current *EMD COTS Deployment Plan*, (335-EMD-series document). The project maintenance philosophy for software is to provide EMD centralized support for developed items and vendor support for COTS software.

Installation

EMD Project software consists of COTS, custom-developed, and science software.

Software maintenance includes:

- Right to use COTS software products..
- Access to software vendor telephone support
- Access to vendors on-line and email support
- Receive patches and upgrades
- The DAAC maintenance activity includes: software configuration management (CM) including support for change control, configuration status accounting, audit activities, and software quality assurance (QA). Each site is the CM authority over its own resources subject to ESDIS delegation of roles for EMD management.

LOG FILES

Log files must be maintained documenting all COTS installations and modifications. These files delineate manufacturer, product, installation date, modification date and all other pertinent configuration data available.

COTS Configuration

The COTS software upgrades are subject to CCB approval before they may be loaded on any platform. EMD Sustaining Engineering notifies the CCB of the upgrade that has been received. The COTS SW Librarian distributes the COTS software upgrade as directed by the CCB. The site Software Maintenance Engineer, Network Administrator, and the System Administrator are responsible for upgrading the software on the host machine and providing follow-up information to the Configuration Management Administrator (CMA). The site Local Maintenance Coordinator will notify the appropriate personnel (Release Installation Team, System

Administrator, Network Administrator, Software Maintenance Engineer) when the COTS software is received and approved by the CCB for installation.

COTS software patches may be provided by the COTS software vendor in response to a DAAC's call requesting assistance in resolving a COTS software problem. The problem may or may not exist at other locations. When a COTS software patch is received directly from a COTS software vendor (this includes downloading the patch from an on-line source), the DAAC's CCB will be informed via CCR prepared by the requesting Operator, System Administrator, Network Administrator, or site Software Maintenance Engineer. It is the responsibility of the Operator, System Administrator, Network Administrator, or site Software Maintenance Engineer to notify the CCB of the patch's receipt, purpose, and installation status and to comply with the CCB decisions. The Operator, System Administrator, Network Administrator, or site Software Maintenance Engineer installs COTS software patches as directed by the CCB.

In addition to providing patches to resolve problems at a particular site, the software vendor will periodically provide changes to COTS software to improve the product; these changes are issued as part of the software maintenance contract. Upgrades are issued to licensees of the basic software package. Therefore, the COTS software upgrades will be shipped to the ILS Property Administrator (PA), who receives and enters them into inventory.

Security

System security architecture must meet the requirements for data integrity, availability, and confidentiality. Security Services meet these requirements by incorporating a variety of mechanisms to establish and verify user accounts, issue and verify passwords, audit user activity, and verify and protect data transfer. To monitor and control access to network services, Security Services use the public domain tool, TCP Wrappers (Note: All DAACs, except for NSIDC do not use TCP Wrappers). Other public domain COTS products — ANLpasswd and Crack— provide additional password protection for local system and network access. The tool Tripwire monitors changes to files and flags any unauthorized changes.

This section defines step-by-step procedures for System Administrators to run the Security Services tools. The procedures assume that the requester's application for a Security process has already been approved by DAAC Management.

Generating Security Reports

User Activity Data

A log is created to keep track of unsuccessful attempts to log into the computer. After a person makes five consecutive unsuccessful attempts to log in, all these attempts are recorded in the file `/var/adm/loginlog`. The procedures assume that the file has been created and the operator has logged on as root.

Reviewing User Activity Data

- 1 At the UNIX prompt type `/usr/bin/logins [-admopstux] [-g group...] [-l login...]` then press the **Return/Enter** key.
 - **-a** Adds two password expiration fields to the display. The fields show how many days a password can remain unused before it automatically becomes inactive, and the date that the password will expire.
 - **-d** Selects logins with duplicate uids.
 - **-m** Displays multiple group membership information.
 - **-o** Formats output into one line of colon-separated fields.
 - **-p** Selects logins with no passwords.
 - **-s** Selects all system logins.
 - **-t** Sorts output by login instead of by uid.
 - **-u** Selects all user logins.

- **-x** Prints an extended set of information about each selected user. The extended information includes home directory, login shell and password aging information, each displayed on a separate line. The password information consists of password status (“PS” for password, “NP” for no password or “LK” for locked). If the login is passworded, status is followed by the date the password was last changed, the number of days required between changes, and the number of days allowed before a change is required. The password aging information shows the time interval that the user will receive a password expiration warning message (when logging on) before the password expires.
 - **-g group** Selects all users belonging to group, sorted by login. Multiple groups can be specified as a comma-separated list. When the **-l** and **-g** options are combined, a user will be listed only once, even if the user belongs to more than one of the selected groups.
 - **-l login** Selects the requested login. Multiple logins can be specified as a comma-separated list. Depending on the nameservice lookup types set in `/etc/nsswitch.conf`, the information can come from the `/etc/passwd` and `/etc/shadow` files and other nameservices. When the **-l** and **-g** options are combined, a user will be listed only once, even if the user belongs to more than one of the selected groups.
- 2 Type **logins -x -l username** then press the **Return/Enter** key.
 - Displays login status for a user.
 - 3 Type **/var/adm/loginlog** then press the **Return/Enter** key.
 - To enable login Logging, this creates the log file **loginlog**.
 - 4 Type **chmod 600 /var/adm/loginlog** then press the **Return/Enter** key.
 - This sets read and write permissions for root on the file.
 - 5 Type **chgrp sys /var/adm/loginlog** then press the **Return/Enter** key.
 - This sets the group to **sys**.
-

User Audit Trail Information

The **audit_startup** script is used to initialize the audit subsystem before the audit daemon is started. This script is configurable by the System Administrator, and currently consists of a series of **auditconfig** commands to set the system default policy, and to download the initial events to class mapping. Type the following command to initialize the audit subsystem:

/etc/security/audit_startup

The audit command is the general administrator’s interface to the audit trail. The audit daemon may be notified to read the contents of the `audit_control` file and re-initialize the current audit directory to the first directory listed in the `audit_control` file or to open a new audit file in the

current audit directory specified in the `audit_control` file as last read by the audit daemon. The audit daemon may also be signaled to close the audit trail and disable auditing. The audit commands are input as shown:

Audit Commands

audit -n then press the **Return/Enter** key.

- Signals audit daemon to close the current audit file and open a new audit file in the current audit directory.

audit -s then press the **Return/Enter** key.

- Signals audit daemon to read the current audit file. The audit daemon stores the information internally.

audit -t then press the **Return/Enter** key.

- Signals audit daemon to close the current audit file, disable audit and die.

praudit -sl *filename* then press the **Return/Enter** key.

- Displays audit output. The print audit command converts the binary audit records into a variety of formats, depending on the options used with the commands. The format of audit files is included in the file `/usr/include/sys/audit.h`. By default, user IDs (UID) and group IDs (GID) are converted to their ACSII representation.

This page intentionally left blank.

Practical Exercise

Introduction

These practical exercises are presented in “day-in-the-life” scenarios relating to system administration activities. They represent real situations that you, as System Administrator, are likely to encounter on a day-to-day basis.

Equipment and Materials

A functioning computer system.

One workstation per student.

Statement of the requirements for the exercise.

Release 7.11 Operations Tools Manual for the EMD Project, 609-EMD-001, one copy per student.

Release 7.11 Mission Operation Procedures for the EMD Project, 611-EMD-001, one copy per student.

System Startup and Shutdown

The EOSDIS system was taken down for maintenance earlier in the day and the maintenance has been completed. You must now bring the system to full operation. Turn on the entire system in the prescribed order.

-or-

Startup the following servers:

- ASE Server
- Server 2
- Server 3

Tape Operations, System Backup and Restore

1. You have received an approved request from the Sustaining Engineering Chief to perform an incremental backup of the ASE Server for files created or modified within the past 48 hours.
2. Determine how many tapes it will take to back up the required data.
3. Prepare the appropriate number of new tapes to accommodate the backup and perform the label and inventory operations on the tapes.
4. Perform the incremental backup.

5. Inform the Sustaining Engineering Chief that the backup has been performed.
6. **xuser** calls you and tells you that she has inadvertently erased the following three files that are critical to her research:
 - file1
 - file2
 - file3
7. She does not remember exactly when they were last modified. Locate the latest versions of each of the files and perform a file restoration.

User Administration

1. Add a user to the system (refer to Figure 34).

UNIX User Registration Request	
<p>REQUESTER INFORMATION:</p> <p>Name: <u>Erica J. Sonnenshein</u></p> <p>Office Phone Number: <u>(301) 999-5555</u></p> <p>E-Mail Address: <u>esonnens@gsfc.nasa.gov</u> Office Location: <u>Bldg. 32</u></p> <p>NEW USER INFORMATION:</p> <p>Name: <u>Peter Kovalkaides</u></p> <p>Office Phone Number: <u>(301) 555-1234</u></p> <p>Home Phone Number: <u>(301) 444-4444</u></p> <p>Organization: <u>GSFC DAAC</u></p> <p>Group Affiliation(s): <u>SMC</u></p> <p>Role(s)/Job(s)/Justification: <u>computer operator w/database access required</u></p> <p>Date of Request: <u>9/17/97</u> Date Required: <u>9/22/97</u></p> <p>Supervisor Approval: _____ Date: _____</p> <p>Ops Supervisor Approval: _____ Date: _____</p>	

Figure 34. UNIX User Registration Request Form

2. The user you just added has called you with the news that he has forgotten his password. Describe the procedures you must follow to receive authorization to change the individual's password. Assuming you have received the appropriate authorizations, change the password to gnu-Uzr.
3. Change the group affiliations for this user to **new-group affiliation**.
4. Peter Kovalkaides sends you an e-mail message informing that the work on his task is complete and requests that you change the access privileges on all files owned by him to READ ONLY for all classes of users to protect the files from changes.
5. You have determined that space on the **xserver** is becoming rather scarce. There are a few large files (*insert-file-names-here*) that need to be deleted, and since **xuser** and Peter Kovalkaides are done with their projects, their home directories need to be moved to *insert-new-location-here*. Perform the procedures that will accomplish these tasks assuming you have received the appropriate authorizations. When you are done, inform the affected users of the changes.

System Maintenance

1. The icon on the Desktop for the ASE Server has turned red. Check the system log to find out what the problem is.
2. The problem in this exercise requires you to restart the ASE server without affecting any of the other subsystems. Perform this task now.

This page intentionally left blank.

Slide Presentation

Slide Presentation Description

The following slide presentation represents the slides used by the instructor during the conduct of this lesson.

This page intentionally left blank.